

# Hitachi Block Storage Driver for OpenStack Newton

---

## User Guide

This guide provides information about installing, configuring, and managing Hitachi Block Storage Driver for OpenStack.

© 2015, 2018 Hitachi, Ltd. All rights reserved.

No part of this publication may be reproduced or transmitted in any form or by any means, electronic or mechanical, including copying and recording, or stored in a database or retrieval system for commercial purposes without the express written permission of Hitachi, Ltd., or Hitachi Vantara Corporation (collectively "Hitachi"). Licensee may make copies of the Materials provided that any such copy is: (i) created as an essential step in utilization of the Software as licensed and is used in no other manner; or (ii) used for archival purposes. Licensee may not make any other copies of the Materials. "Materials" mean text, data, photographs, graphics, audio, video and documents.

Hitachi reserves the right to make changes to this Material at any time without notice and assumes no responsibility for its use. The Materials contain the most current information available at the time of publication.

Some of the features described in the Materials might not be currently available. Refer to the most recent product announcement for information about feature and product availability, or contact Hitachi Vantara Corporation at [https://support.hitachivantara.com/en\\_us/contact-us.html](https://support.hitachivantara.com/en_us/contact-us.html).

**Notice:** Hitachi products and services can be ordered only under the terms and conditions of the applicable Hitachi agreements. The use of Hitachi products is governed by the terms of your agreements with Hitachi Vantara Corporation.

By using this software, you agree that you are responsible for:

1. Acquiring the relevant consents as may be required under local privacy laws or otherwise from authorized employees and other individuals; and
2. Verifying that your data continues to be held, retrieved, deleted, or otherwise processed in accordance with relevant laws.

**Notice on Export Controls.** The technical data and technology inherent in this Document may be subject to U.S. export control laws, including the U.S. Export Administration Act and its associated regulations, and may be subject to export or import regulations in other countries. Reader agrees to comply strictly with all such regulations and acknowledges that Reader has the responsibility to obtain licenses to export, re-export, or import the Document and any Compliant Products.

Hitachi is a registered trademark of Hitachi, Ltd., in the United States and other countries.

All other trademarks, service marks, and company names in this document or website are properties of their respective owners.

---

# Contents

<b>Preface.....</b>	<b>7</b>
Intended audience.....	7
Software version.....	7
Document conventions.....	7
Release notes.....	9
Changes made in this revision.....	9
Referenced documents .....	9
Related documents .....	10
Conventions for storage capacity values.....	11
Getting help.....	12
Comments.....	12
 <b>Chapter 1: Overview.....</b>	 <b>13</b>
System Configuration.....	13
Supported Cinder functions .....	14
Support for additional OpenStack operations .....	15
Backend storage management configuration.....	16
Volume operations.....	16
Copy operations .....	17
Volume attachment.....	19
Backup operations.....	20
Manage and unmanage a volume.....	21
Volume migration .....	21
 <b>Chapter 2: System requirements.....</b>	 <b>22</b>
Operating systems.....	22
OpenStack.....	22
Storage devices.....	22
Storage firmware versions.....	22
Software.....	23
Prerequisite packages.....	23
Storage management software .....	23
Storage software licenses.....	24
Software restrictions.....	24

## Chapter 3: Installation and configuration.....25

Installation and setup workflow.....	25
Supported configurations for Block Storage Driver for OpenStack.....	25
Management software restrictions .....	27
Environment setup.....	27
Connect nodes.....	27
Single node configuration.....	28
Controller node without I/O data paths .....	28
Configure node setting.....	30
About the communication mode of the Configuration Manager REST API server .....	30
Configure storage resources.....	31
Common resources .....	31
Fibre Channel connectivity .....	32
iSCSI connectivity .....	34
Configure Configuration Manager REST API server .....	35
Secure your storage system password.....	36
Install Block Storage Driver for OpenStack .....	37
Installation prerequisites .....	37
Block Storage Driver for OpenStack installation for Red Hat and SUSE.....	37
Block Storage Driver for OpenStack installation for Mirantis and Ubuntu....	38
Initial setup.....	39
Add a Block Storage Driver for OpenStack configuration.....	39
Using Director (Red Hat OpenStack Platform).....	39
Using Crowbar (SUSE OpenStack Cloud).....	39
Using FUEL (Mirantis OpenStack).....	40
Using MAAS (Ubuntu OpenStack).....	40
Linking a volume type and a backend.....	40
Edit cinder.conf.....	41
Restart Cinder.....	42
Verify Block Storage Driver for OpenStack installation.....	42
Update the Block Storage Driver for OpenStack.....	44
Update the Block Storage Driver for OpenStack software for Red Hat and SUSE .....	44
Update the Block Storage Driver for OpenStack software for Mirantis and Ubuntu.....	44
Uninstall Block Storage Driver for OpenStack.....	45
Live migration .....	45
Configure multipathing.....	46
Configure high availability.....	47
High availability configuration overview.....	47

Pacemaker configurations for Cinder volumes.....	47
Build high availability environment of controller node .....	48
Recoverable failures.....	49
Handling high availability post-failover .....	49
<b>Chapter 4: Hitachi extended functions.....</b>	<b>51</b>
Copy methods .....	51
Maximum number of copy pairs.....	54
Port assignment using extra specs.....	54
Port scheduler.....	54
Data deduplication and compression.....	56
Enabling deduplication and compression .....	57
Creating a volume with dedupe/comp enabled.....	57
Deleting a volume with dedupe/comp enabled.....	58
<b>Chapter 5: Parameters.....</b>	<b>59</b>
Block Storage Driver for OpenStack specific parameters .....	59
Cinder-specific parameters.....	68
<b>Chapter 6: Troubleshooting.....</b>	<b>73</b>
Check the version of Block Storage Driver for OpenStack.....	73
hbsdgetinfo command.....	73
Configuration Manager logs.....	78
Openstack-cinder-volume service does not start.....	78
Volume (snapshot) cannot be created.....	78
Volume (snapshot) cannot be attached.....	79
Volume operations fail in a multi-controller node environment.....	79
Volume attach and detach operations fail.....	79
Volume detach operation fails.....	79
Volume attach performance issues after HBA replacement.....	79
Volume deletion causes error status.....	80
Contacting Hitachi Vantara Corporation customer support.....	80
<b>Chapter 7: Messages.....</b>	<b>81</b>
Message output format.....	81
List of messages .....	82
Messages output by the command <code>hbsdgetinfo</code> .....	102
Messages output by the installer.....	103
<b>Appendix A: OpenStack overview.....</b>	<b>104</b>
About OpenStack.....	104
Cinder overview.....	105
Cinder commands.....	105

OpenStack commands.....	105
<b>Appendix B: Block Storage Driver for OpenStack License.....</b>	<b>106</b>
<b>Glossary.....</b>	<b>107</b>

---

## Preface

This guide provides overview of and technical information for installing, configuring, and administering Hitachi Block Storage Driver for OpenStack.

### Intended audience

This document is intended for operators and administrators who configure and operate cloud systems using the following software tools:

- Red Hat OpenStack Platform
- SUSE OpenStack Cloud
- Mirantis OpenStack
- Ubuntu OpenStack
- Configuration Manager REST API

This document assumes they have basic knowledge of Linux operating systems.

### Software version

This document applies to Block Storage Driver for OpenStack version 3.2.0 or later for Newton.




### Document conventions


This document uses the following typographic conventions:

Convention	Description
<b>Bold</b>	<ul style="list-style-type: none"><li>▪ Indicates text in a window, including window titles, menus, menu options, buttons, fields, and labels. Example: Click <b>OK</b>.</li><li>▪ Indicates emphasized words in list items.</li></ul>

Convention	Description
<i>Italic</i>	<ul style="list-style-type: none"> <li>Indicates a document title or emphasized words in text.</li> <li>Indicates a variable, which is a placeholder for actual text provided by the user or for output by the system. Example: <pre>pairdisplay -g group</pre> <p>(For exceptions to this convention for variables, see the entry for angle brackets.)</p> </li> </ul>
Monospace	Indicates text that is displayed on screen or entered by the user. Example: <code>pairdisplay -g oradb</code>
< > angle brackets	Indicates variables in the following scenarios: <ul style="list-style-type: none"> <li>Variables are not clearly separated from the surrounding text or from other variables. Example: <pre>Status-&lt;report-name&gt;&lt;file-version&gt;.csv</pre> </li> <li>Variables in headings.</li> </ul>
[ ] square brackets	Indicates optional values. Example: [ a   b ] indicates that you can choose a, b, or nothing.
{ } braces	Indicates required or expected values. Example: { a   b } indicates that you must choose either a or b.
vertical bar	Indicates that you have a choice between two or more options or arguments. Examples: [ a   b ] indicates that you can choose a, b, or nothing. { a   b } indicates that you must choose either a or b.

This document uses the following icons to draw attention to information:

Icon	Label	Description
	Note	Calls attention to important or additional information.
	Tip	Provides helpful information, guidelines, or suggestions for performing tasks more effectively.
	Caution	Warns the user of adverse conditions and/or consequences (for example, disruptive operations, data loss, or a system crash).

Icon	Label	Description
	WARNING	Warns the user of a hazardous situation which, if not avoided, could result in death or serious injury.

## Release notes

Read the release notes before installing and using this product. They may contain requirements or restrictions that are not fully described in this document or updates or corrections to this document. Release notes are available on Hitachi Vantara Support Connect: <https://knowledge.hitachivantara.com/Documents>.

## Changes made in this revision

- The functionalities of Block Storage Driver for OpenStack version 6.1.0 have been backported to OpenStack Newton with the following exceptions.
  - CTG(Consistency group) and GVG(Generic volume group) are not supported.
  - "Revert to snapshot" function is not supported.
  - Multi-attach is not supported.
  - The `hitachi_ldev_range` parameter can be specified when the `hitachi_storage_cli` parameter is set to `SIMPLE_REST`.
  - The `hitachi_rest_pair_target_ports` parameter can be specified only when the `hitachi_target_ports` parameter is not specified.
  - The `hitachi_shared_targets` parameter is not supported.
  - `auto` cannot be specified for the `max_over_subscription_ratio` parameter.
- The software the Block Storage Driver for OpenStack uses to manage storage systems has changed from the Command Control Interface (CCI) to the Configuration Manager REST API.
- HUS VM and VSP have been removed from supported storage systems.
- VSP F350, F370, F700, F900, and VSP G350, G370, G700, G900 have been added to supported storage systems.

## Referenced documents

The documents below are referenced in this document or contain more information about the features described in this document.

### Hitachi Vantara documents

Hitachi Command Suite Configuration Manager REST API: *REST API Reference Guide*, MK-92HC229

Hitachi Virtual Storage Platform F1500 and Hitachi Virtual Storage Platform G1000, G1500: *Provisioning Guide for Open Systems: Hitachi Virtual Storage Platform G1000, G1500, and F1500*, MK-92RD8014

Hitachi Virtual Storage Platform F400, F600, F800 and Hitachi Virtual Storage Platform G400, G600, G800: *Provisioning Guide: Hitachi Virtual Storage Platform Gx00 and Fx00 Models*, MK-94HM8014

Hitachi Virtual Storage Platform F350, F370, F700, F900 and Hitachi Virtual Storage Platform G350, G370, G700, G900: *Provisioning Guide: Hitachi Virtual Storage Platform G/F350, G/F370, G/F700, G/F900*, MK-97HM85026

Hitachi Vantara Support Connect, <https://knowledge.hitachivantara.com/Documents>

## Related documents

The documents below are related to this document or contain more information about features described in this document.

### Hitachi Vantara documents

Common to all storage systems: *Thin Image User Guide: Hitachi Virtual Storage Platform F series and G series*, MK-97HM85032

Hitachi Virtual Storage Platform F1500 and Hitachi Virtual Storage Platform G1000, G1500:

- *System Administrator Guide: Hitachi Virtual Storage Platform G1x00 and F1500*, MK-92RD8016
- *Hardware Guide: Hitachi Virtual Storage Platform G1000,G1500, and Hitachi Virtual Storage Platform F1500*, MK-92RD8007

Hitachi Virtual Storage Platform F400, F600, F800 and Hitachi Virtual Storage Platform G400, G600, G800:

- *System Administrator Guide: Hitachi Virtual Storage Platform Gx00 and Fx00*, MK-94HM8016
- *Hardware Reference Guide: Hitachi Virtual Storage Platform F400, F600*, MK-94HM8045
- *Hardware Reference Guide: Hitachi Virtual Storage Platform F800*, MK-94HM8046
- *Hardware Reference Guide: Hitachi Virtual Storage Platform G200*, MK-94HM8020
- *Hardware Reference Guide: Hitachi Virtual Storage Platform G400, G600*, MK-94HM8022
- *Hardware Reference Guide: Hitachi Virtual Storage Platform G800*, MK-94HM8026

Hitachi Virtual Storage Platform F350, F370, F700, F900 and Hitachi Virtual Storage Platform G350, G370, G700, G900:

- *System Administrator Guide: Hitachi Virtual Storage Platform G/F350, G/F370, G/F700, G/F900, MK-97HM85028*
- *Hardware Reference Guide: Hitachi Virtual Storage Platform F350 and F370, MK-97HM85016*
- *Hardware Reference Guide: Hitachi Virtual Storage Platform F700, MK-97HM85017*
- *Hardware Reference Guide: Hitachi Virtual Storage Platform F900, MK-97HM85018*
- *Hardware Reference Guide: Hitachi Virtual Storage Platform G350 and G370, MK-97HM85012*
- *Hardware Reference Guide: Hitachi Virtual Storage Platform G700, MK-97HM85013*
- *Hardware Reference Guide: Hitachi Virtual Storage Platform G900, MK-97HM85014*

### OpenStack

- *OpenStack Cloud Administrator Guide*
- *OpenStack Command-Line Interface Reference*
- *OpenStack Configuration Reference*
- *Red Hat OpenStack Platform Product Documentation*
- *SUSE OpenStack Cloud Product Manual*
- *Mirantis OpenStack Product Documentation*
- *Ubuntu OpenStack Documentation*

## Conventions for storage capacity values

Physical storage capacity values (for example, disk drive capacity) are calculated based on the following values:

Physical capacity unit	Value
1 kilobyte (KB)	1,000 (10 <sup>3</sup> ) bytes
1 megabyte (MB)	1,000 KB or 1,000 <sup>2</sup> bytes
1 gigabyte (GB)	1,000 MB or 1,000 <sup>3</sup> bytes
1 terabyte (TB)	1,000 GB or 1,000 <sup>4</sup> bytes
1 petabyte (PB)	1,000 TB or 1,000 <sup>5</sup> bytes
1 exabyte (EB)	1,000 PB or 1,000 <sup>6</sup> bytes

Logical capacity values (for example, logical device capacity, cache memory capacity) are calculated based on the following values:

Logical capacity unit	Value
1 block	512 bytes
1 cylinder	Mainframe: 870 KB Open-systems: ▪ OPEN-V: 960 KB ▪ Others: 720 KB
1 KB	1,024 ( $2^{10}$ ) bytes
1 MB	1,024 KB or $1,024^2$ bytes
1 GB	1,024 MB or $1,024^3$ bytes
1 TB	1,024 GB or $1,024^4$ bytes
1 PB	1,024 TB or $1,024^5$ bytes
1 EB	1,024 PB or $1,024^6$ bytes

## Getting help

[Hitachi Vantara Support Connect](#) is the destination for technical support of products and solutions sold by Hitachi Vantara. To contact technical support, log on to Hitachi Vantara Support Connect for contact information: [https://support.hitachivantara.com/en\\_us/contact-us.html](https://support.hitachivantara.com/en_us/contact-us.html).

[Hitachi Vantara Community](#) is a global online community for Hitachi Vantara customers, partners, independent software vendors, employees, and prospects. It is the destination to get answers, discover insights, and make connections. **Join the conversation today!** Go to [community.hitachivantara.com](https://community.hitachivantara.com), register, and complete your profile.

## Comments

Please send us your comments on this document to [doc.comments@hitachivantara.com](mailto:doc.comments@hitachivantara.com). Include the document title and number, including the revision level (for example, -07), and refer to specific sections and paragraphs whenever possible. All comments become the property of Hitachi Vantara Corporation.


**Thank you!**

# Chapter 1: Overview

Block Storage Driver for OpenStack is based on the OpenStack Block Storage architecture (Cinder) and it enables you to provide storage services that use high-performance and high-reliability Hitachi storage systems to build and deliver Infrastructure as a Service (IaaS).

## System Configuration

A typical system configuration for Block Storage Driver for OpenStack contains the main components shown in the figure below. This figure is an example of a multi-node configuration where the controller node and the compute nodes are configured on different nodes.



### Controller node

A server that manages cloud systems. The cinder-volume services run on this node. Install and use Block Storage Driver for OpenStack on this node.

**Compute node**

A server managed by the controller node.

**Configuration Manager REST API server**

A server that receives REST API requests from Block Storage Driver for OpenStack, issues commands to the storage system, and returns the execution results. The REST API server can be installed independently or installed together as a part of the Hitachi Command Suite.

**Backend storage system**

A storage system managed by Cinder. Block Storage Driver for OpenStack uses thin-provisioned volumes (DP-VOLs) from Hitachi Dynamic Provisioning (DP) pools as backend storage. To use multiple DP pools, register each DP pool as a separate backend storage system.

**LDEV**

An individual logical data volume (on multiple drives in a RAID configuration) in a storage system.

**Volume**

Data unit managed by Block Storage Driver for OpenStack.

## Supported Cinder functions

The following table lists the Cinder operations supported by Block Storage Driver for OpenStack.

Function	Description
Create Volume	Creates a volume.
Delete Volume	Deletes a volume.
Attach Volume	Connects a volume to a VM instance.
Detach Volume	Disconnects a target volume from a VM instance.
Extend Volume	Resizes a volume.
Create Snapshot <sup>1</sup>	Creates a snapshot that stores point-in-time data.
Delete Snapshot	Deletes a snapshot.
List Snapshot	Lists snapshots.
Create Volume from Snapshot	Creates a volume with the same content as that of a snapshot.

Function	Description
Create Volume from Image	Retrieves image stored from Glance and loads it into the specified volume. A VM can be started based on the stored image.
Create Volume from Volume (Clone)	Creates a volume and then stores the data from the source volume.
Create Image from Volume	Creates an image from a volume and uploads the image (Glance).
Volume Migration (host assisted)	Moves a volume to another DP pool managed by another storage system.
Over subscription	Uses thin provisioning to manage the capacity of the storage system.
Volume Migration (storage assisted)	Moves a volume to another DP pool.
Backup using temp Snapshot	Uses a temporary snapshot or volume to perform non-disruptive backup. As a separate feature, this function can be used to back up snapshots. The Cinder backup service must be running.
Backup Volume	Backs up a volume to Swift. The Cinder backup service must be running.
Restore Backup	Restores data to a specified volume from Swift. The Cinder backup service must be running.
Manage Volume	Adds an LDEV created by a different OpenStack system to the volumes managed by Cinder.
Unmanage Volume	Removes a volume created by Cinder from Cinder management.
Retype Volume	Changes the volume type.
<b>Notes:</b> 1. Snapshots are created using Thin Image (Snapshot).	

## Support for additional OpenStack operations

The following table lists the OpenStack operations supported by Block Storage Driver for OpenStack.


OpenStack operation	Description
Live Migration	Moves a volume managed by Block Storage Driver for OpenStack and attached to a running VM from one compute node to another.
Multipath for I/O path	Multipath enabled for volumes managed by Block Storage Driver for OpenStack.
High availability for Cinder volume services	You can use the high availability cluster software to set the cinder-volume service in a redundant active-standby configuration. High availability is not supported for SUSE OpenStack Cloud or Mirantis OpenStack.
Fibre Channel Zone Manager	When a volume managed by Block Storage Driver for OpenStack is attached to a VM via Fibre Channel, Fibre Channel zoning can automatically be created or deleted between the compute node and the storage system during a volume attach or detach operation, respectively. See <a href="https://docs.openstack.org/newton/config-reference/block-storage/fc-zoning.html">https://docs.openstack.org/newton/config-reference/block-storage/fc-zoning.html</a> for how to specify settings.

## Backend storage management configuration

Block Storage Driver for OpenStack uses thin-provisioned volumes (DP-VOLs) from DP pools as backend storage (a Hitachi storage feature that provides virtual volume capability). To use multiple DP pools, register each DP pool as a separate backend storage system. Each DP pool will be identified in the `cinder.conf` file.

## Volume operations

Block Storage Driver for OpenStack provides volume operation functions for managing LDEVs (logical devices or logical units) in the backend storage (DP pools). The figure below shows an overview of volume operations.



**Figure 1 Overview of volume operations**

### Create and delete a volume

When Block Storage Driver for OpenStack receives the Cinder create volume request, it creates a virtual volume (DP-VOL) as a logical device (LDEV) from the DP pool. DP-VOLs allow the storage to be provisioned on an as-needed basis. Volumes can be deleted by using the Cinder delete volume command.

### Extend a volume


Block Storage Driver for OpenStack allows you to resize the DP-VOL, ensuring that the volume can be expanded to meet changing business requirements.



**Note:** You cannot expand DP-VOLs created by using Thin Image (Clone) during asynchronous copying or DP-VOLs that have pair volumes that were created by using Thin Image (Snapshot).

## Copy operations

When Block Storage Driver for OpenStack receives a Cinder copy volume request, Block Storage Driver for OpenStack copies the volume in full by using Thin Image (Clone), and takes a point-in-time snapshot of the volume by using Thin Image (Snapshot).



**Figure 2 Snapshot operation example**

Before you attempt to copy a volume attached to a VM, stop I/O on the VM.

The following table describes the copy methods available for Block Storage Driver for OpenStack. To perform copy operations, you will need a license for the Thin Image software product. A maximum of 1,024 clones and snapshots can be created for each volume.

Copy method	Description
Thin Image (Clone)	All data in the copy source volume (DP-VOL) is asynchronously copied to the destination volume. Both volumes can be used during the asynchronous copy.
Thin Image (Snapshot)	Differential data with the copy destination volume is stored as needed in a virtual volume (V-VOLv2) as an LDEV. Both volumes can be used. The virtual volume (V-VOLv2) can be used in a cascade configuration.

**Create a snapshot**

Upon receiving a Cinder create snapshot request, Block Storage Driver for OpenStack creates an LDEV linked to the snapshot, and then copies the snapshot data from the volume to the LDEV by Thin Image (Snapshot). The snapshot cannot be attached to a VM, but it can be kept as a data backup.

**Create a volume from a snapshot**


Upon receiving a Cinder create volume from snapshot request, Block Storage Driver for OpenStack creates an LDEV linked to the volume, and then stores the specified snapshot data in the LDEV by using one of the available copy methods (see the previous table).

**Create a volume from a volume (clone)**

Upon receiving a Cinder create volume from volume (clone) request, Block Storage Driver for OpenStack creates an LDEV linked to the volume, and then stores the specified volume data in the LDEV by using one of the available copy methods (see the previous table). Volume cloning is useful when multiple users use the same data.

## Volume attachment

Block Storage Driver for OpenStack supports storage attachment capability for storage systems that use the following protocols: Fibre Channel, iSCSI, and Fibre Channel over Ethernet. Block Storage Driver for OpenStack supports multipath configurations. The port scheduler function is also supported. If this function is used, then, when volumes are attached, the active WWNs on the obtained compute nodes are distributed and registered to the host groups of each port of the storage system. Volumes will be assigned based on this attachment information. The following figure shows an overview of the volume attachment operations.



**Figure 3 Volume attachment**

Upon receiving a Cinder attach volume request, Block Storage Driver for OpenStack attaches a volume to a VM in the specified compute node. Block Storage Driver for OpenStack then directly connects the Hitachi storage system and the compute node. This allows the VM to access the attached volume to store data. The volume can also be detached from the VM. The volume can be attached again to another VM. Block Storage Driver for OpenStack allows volume attach and detach operations in a multipath configuration.

## Backup operations

You can use standard Cinder functions to back up or restore volumes created by Block Storage Driver for OpenStack. If you restore a volume from external storage by using standard OpenStack functions, the metadata for the volume will be overwritten. To prevent this, perform the following procedure to restore a volume from external storage.

### Procedure

1. Create a volume to which the data is to be restored. Note the LDEV metadata value, which can be acquired by using the `cinder metadata-show` command.
2. Restore the volume from external storage. If the volume ID of the restore target is not specified, or if the specified volume ID is different from the backed-up volume, the type and LDEV metadata for the restore target volume will not be consistent with the actual LDEV number.

3. Remove the metadata by using the **cinder metadata** command. Use the same command to restore the type and LDEV metadata values. For details about this command, see the help messages or the Command-Line Interface Reference.

## Manage and unmanage a volume

If you plan to move a volume from one OpenStack Cinder instance to another, you can use the **cinder manage** and **cinder unmanage** commands. Specify `source-id <LDEV Number>` in the `--id-type` option.

## Volume migration

When Block Storage Driver for OpenStack receives a Cinder migrate volume request, a virtual volume (DP-VOL) is created as a logical device (LDEV) in the pool specified as the migration destination, and then the data on the source volume is copied.

When volumes are migrated within the same storage system, storage-assisted copy processing is performed. When volumes are migrated between different storage systems, host-assisted copy processing is performed.

---

## Chapter 2: System requirements

Before setting up your environment for use with Block Storage Driver for OpenStack, review the supported hardware, software, and license requirements.

### Operating systems

For details on the supported operating systems, see the Hitachi Block Storage OpenStack driver support matrix at: [https://support.HitachiVantara.com/en\\_us/interoperability.html](https://support.HitachiVantara.com/en_us/interoperability.html).

### OpenStack

For details on the supported OpenStack, see the Hitachi Block Storage OpenStack driver support matrix at: [https://support.HitachiVantara.com/en\\_us/interoperability.html](https://support.HitachiVantara.com/en_us/interoperability.html).

### Storage devices

For details on the supported storage systems, see the Hitachi Block Storage OpenStack driver support matrix at: [https://support.HitachiVantara.com/en\\_us/interoperability.html](https://support.HitachiVantara.com/en_us/interoperability.html).

### Storage firmware versions

The following table provides the Hitachi storage device firmware versions for each Block Storage Driver for OpenStack version.

Storage model	Firmware version
VSP F1500 VSP G1000, VSP G1500	80-05-43 or later
VSP F400, F600, F800 VSP G200, G400, G600, G800	83-04-43 or later
VSP F350, F370, F700, F900 VSP G350, G370, G700, G900	88-01-04 or later

## Software

This section describes the software required for each version of the Block Storage Driver for OpenStack.

### Prerequisite packages

The following table lists the prerequisite packages for Block Storage Driver for OpenStack.

Distribution	Node	Item	Contents
Red Hat	Controller node	Linux environment	sysfsutils <sup>1</sup> , sg3_utils <sup>1</sup> , iscsi-initiator-utils <sup>2</sup> , device-mapper-multipath <sup>3</sup>
	Compute node	Linux environment	sysfsutils <sup>1</sup> , sg3_utils <sup>1</sup> , iscsi-initiator-utils <sup>2</sup> , device-mapper-multipath <sup>3</sup>
SUSE	Controller node	Linux environment	sysfsutils <sup>1</sup> , sg3_utils <sup>1</sup> , open-iscsi <sup>2</sup> , multipath-tools <sup>3</sup>
	Compute node	Linux environment	sysfsutils <sup>1</sup> , sg3_utils <sup>1</sup> , open-iscsi <sup>2</sup> , multipath-tools <sup>3</sup>
Ubuntu and Mirantis	Controller node	Linux environment	sysfsutils <sup>1</sup> , sg3_utils <sup>1</sup> , open-iscsi <sup>2</sup> , multipath-tools <sup>3</sup>
	Compute node	Linux environment	sysfsutils <sup>1</sup> , sg3_utils <sup>1</sup> , open-iscsi <sup>2</sup> , multipath-tools <sup>3</sup>
<b>Notes:</b> <ol style="list-style-type: none"> <li>1. For configuring FC.</li> <li>2. For configuring iSCSI.</li> <li>3. For configuring multipath.</li> </ol>			

For the supported storage platforms and the distribution releases, see: [https://support.HitachiVantara.com/en\\_us/interoperability.html](https://support.HitachiVantara.com/en_us/interoperability.html).

### Storage management software

The following table shows the versions of Configuration Manager REST API that can be used to manage Hitachi storage devices.

Storage model	Configuration Manager REST API Version
VSP F1500	8.5.4-00 or later

Storage model	Configuration Manager REST API Version
VSP G1000, VSP G1500 VSP F400, F600, F800 VSP G200, G400, G600, G800	
VSP F350, F370, F700, F900 VSP G350, G370, G700, G900	8.5.6-00 or later

## Storage software licenses

The following software licenses are required:

- Hitachi Storage Virtualization Operating System (SVOS)
  - Hitachi LUN Manager
  - Hitachi Dynamic Provisioning
- Hitachi Local Replication (Hitachi Thin Image)

The following software licenses are optional:

- Deduplication and compression

## Software restrictions

Do not use Hitachi Dynamic Link Manager (HDLM) in controller nodes or compute nodes. Use DM-Multipath instead.

---

## Chapter 3: Installation and configuration

This chapter describes how to install and configure Block Storage Driver for OpenStack.

### Installation and setup workflow

This topic describes the workflow for preparing, installing and configuring Block Storage Driver for OpenStack.

#### Prepare for installation


1. Connect nodes and the storage devices. See [Connect nodes \(on page 27\)](#).
2. Configure the node settings. See [Configure node setting \(on page 30\)](#).
3. Configure the node settings for storage resources used by Block Storage Driver for OpenStack. See [Configure storage resources \(on page 31\)](#).
4. Install and configure the Configuration Manager REST API server. See [Configure Configuration Manager REST API server \(on page 35\)](#).

#### Install Block Storage Driver for OpenStack

1. Check the required memory size and disk space, and verify the OpenStack package installation. See [Installation prerequisites \(on page 37\)](#).
2. Install Block Storage Driver for OpenStack. See [Install Block Storage Driver for OpenStack \(on page 37\)](#).
3. Configure Block Storage Driver for OpenStack. See [Initial setup \(on page 39\)](#).
4. Restart Block Storage Driver for OpenStack. See [Restart Cinder \(on page 42\)](#).
5. Verify the installation. See [Verify Block Storage Driver for OpenStack installation \(on page 42\)](#).

### Supported configurations for Block Storage Driver for OpenStack

Hitachi recommends an active-standby cluster configuration of OpenStack controller nodes and the Configuration Manager REST API servers. The following figure illustrates such a high-availability configuration.



The following table describes valid OpenStack system configurations.

Configuration	Description
Single-controller configuration	This configuration has a single controller node.
Active-standby configuration	This configuration has multiple controller nodes. In this configuration, only one node on which the cinder-volume service is running is an active node. The other nodes are standby nodes. The storage system is shared amongst all nodes.
<b>Note:</b> Services other than the cinder-volume service can be used in an active-active configuration in accordance with OpenStack recommendations.	

The following table describes the valid system configurations of the Configuration Manager REST API when used with Block Storage Driver for OpenStack.

Configuration	Description
Single-server configuration	This configuration has one Configuration Manager REST API server. You can install the Configuration Manager REST API on a controller node. For the prerequisites for installing the Configuration Manager REST API on a controller node, see <i>System Requirements</i> for Hitachi Command Suite.

Configuration	Description
Active-standby configuration	This configuration has multiple Configuration Manager REST API servers. Only one server is an active server, and the other servers are standby servers.

For details about high-availability cluster configurations of the Configuration Manager REST API, see the [Hitachi Command Suite Configuration Manager REST API Reference Guide](#).

## Management software restrictions

Block Storage Driver for OpenStack does not lock storage systems. For this reason, if storage resources are also registered with another management software, an error might occur due to management conflicts. To avoid such errors, you can use the following parameters to specify resources that can be used by Block Storage Driver for OpenStack: `hitachi_ldev_range` to specify a range of LDEV IDs.

Do not use another management software to perform operations on the resources specified by this parameter.

You can use Configuration Manager REST API to set up resource groups to configure access control on resources managed by various management software. For details, see the description of resource groups in the [Hitachi Command Suite Configuration Manager REST API Reference Guide](#).


## Environment setup

It is necessary to configure the storage device to allow Block Storage Driver for OpenStack to use it. Refer to the documentation provided with the storage device for details.

## Connect nodes

Connect the controller nodes and compute nodes to the ports of the storage device. The compute nodes use the ports of the storage device as data paths. You can use Block Storage Driver for OpenStack to manage both configurations in which controller nodes and compute nodes use the same ports of a storage device, and configurations in which controller nodes and compute nodes use different ports. Design the connection environment based on your operation policy.

The following figure shows a Fibre Channel (FC) connection example:



**Figure 4 Connection example of node configuration**

The ports of a storage device can be shared with other management software.


## Single node configuration

Block Storage Driver for OpenStack allows single node configurations where a single server is configured to serve the role of the controller node and the compute node. There are a few operation restrictions to note for a single node environment. These operations cause I/O disruptions and require you to detach a volume to perform the operation, and reattach the volume.

If a DP-VOL is attached, you cannot copy the volume to images.

## Controller node without I/O data paths

You can use the configuration on the Controller node without I/O data paths, as shown in the following image. This configuration is a viable solution if you do not want to use Fibre Channel ports for management.



**Figure 5 Connection example without I/O data paths for controller node**

Use the following settings to configure the controller node without I/O data path.

- Specify the `hitachi_compute_target_ports` parameter.
- Specify the `hitachi_rest_pair_target_ports` parameter.
- Do not specify the `hitachi_target_ports` parameter.

The following operations are not supported by the controller node without I/O data paths:

- Perform a volume migration (host assisted)
- Create a volume from an image
- Create an image from a volume
- Back up a volume
- Restore a backup
- Retype a volume

## Configure node setting

You can use the OpenStack configuration installer provided by each distribution to build the controller node and compute nodes beforehand. It is recommended to use a multi-node configuration in which the controller node and the compute nodes use separate data paths. Some OpenStack configuration installers might require you to specify a Cinder driver when deploying a Cinder component. When prompted, specify another driver such as NFS (as you cannot select Block Storage Driver for OpenStack at this time) and install the Cinder driver after the deployment. Refer to online resources for the usage of the OpenStack configuration installer provided by each distribution. After building the controller node and the compute nodes, configure each node as described in the following table.

Node	Items	Instruction
Controller node	my_ip for cinder service ( <code>/etc/cinder/cinder.conf</code> )	Specify a unique value for the IPv4 address for the management LAN of the node.
	Initiator IQN ( <code>/etc/iscsi/initiatorname.iscsi</code> )	Specify a unique value for the Initiator IQN. This item is for an iSCSI connection.
Compute node	my_ip for nova compute service ( <code>/etc/nova/nova.conf</code> )	Specify a unique value for the IPv4 address for the management LAN of the node.
	Initiator IQN ( <code>/etc/iscsi/initiatorname.iscsi</code> )	Specify a unique value for the Initiator IQN. This item is for an iSCSI connection.

## About the communication mode of the Configuration Manager REST API server

The Block Storage Driver for OpenStack uses Configuration Manager REST API server for storage operations. The Block Storage Driver for OpenStack supports both in-band and out-of-band methods.

In the in-band management method, the Configuration Manager REST API server connects to the storage system through a SAN.

In the out-of-band management method, the Configuration Manager REST API server connects to the storage system through a LAN. This is the default communication mode for the Configuration Manager REST API server.

If the out-of-band method is used to connect the Configuration Manager REST API server and the storage system, set the `isSecure` property to `True` to encrypt communications between the Configuration Manager REST API server and the storage system. For the setting, see Changing the communication mode of the REST API server in [Hitachi Command Suite Configuration Manager REST API Reference Guide](#).

## Configure storage resources

### Common resources

The following table describes resource requirements for storage systems:

Resource type	Contents
All resources	All storage resources, such as DP pools and host groups, must have a name in order for the driver to use them (name fields cannot be left blank).
LDEVs	If virtual LDEV ID is assigned for the LDEVs used by Block Storage Driver for OpenStack, a volume operation might fail. If you specify <code>hitachi_ldev_range</code> parameter, do not assign virtual LDEV ID for the ldev range specified by <code>hitachi_ldev_range</code> parameter. If you do not specify <code>hitachi_ldev_range</code> parameter, do not set virtual LDEV ID for all the LDEVs used by Block Storage Driver for OpenStack.
Resource groups	If using a new resource group for exclusive use by an OpenStack system, create a new resource group, and assign the necessary resources, such as LDEVs (including LDEVs for a command device or pool), port, and host group (iSCSI target) to the created resource group.
User accounts	<p>To access the storage system from the driver, you must create an account and be assigned to a user group with the following roles:</p> <ul style="list-style-type: none"> <li>Storage Administrator (View Only)</li> <li>Storage Administrator (Provisioning)</li> <li>Storage Administrator (Local Copy)</li> <li>Storage Administrator (Performance Management)</li> </ul> <p>The resource group to be used must be assigned to the user group. You can also use the built-in Storage Administrator (View &amp; Modify) user group.</p>

Resource type	Contents
DP Pool	<ul style="list-style-type: none"> <li>Create a DP pool that is used by Block Storage Driver for OpenStack backend. The driver manages virtual capacity (capacity reserved for over-provisioning of the actual pool capacity). However you can set the percentage of DP-VOL capacity that can be created to the total capacity of the pool as the subscription limit. This can help prevent DP-VOL blocking caused by a full pool. For example, when the subscription limit is set to 100%, the total DP-VOL capacity is equal to the DP pool capacity. To set the subscription limit, set the <code>hitachi_over_subscription</code> parameter to <code>True</code> and specify the ratio by the <code>max_over_subscription_ratio</code> parameter if the storage system model is VSP F350, F370, F700, F900, or VSP G350, G370, G700, G900. Otherwise, set the subscription limit on the storage system.</li> <li>Use a pool that is not assigned to a virtual storage machine. You cannot use DP-VOLs that are assigned to a virtual storage machine or volumes that have been migrated from another system using nondisruptive migration.</li> </ul>
TI pool	Normally, you do not need to create a TI pool. In this case, differential data is stored in the DP pool. If you have a particular reason to store differential data for volumes and snapshots in a dedicated pool, create a TI pool.

## Fibre Channel connectivity

The following table describes Fibre Channel (FC) storage configuration requirements.

Resource type	Contents
Ports	<ul style="list-style-type: none"> <li>Enable Port Security for the port used by the driver.</li> <li>To use the port scheduler function, enable fabric, and then set Point to Point (P to P) for Connection Type.</li> <li>If you change the port configuration used by the driver for connection, restart the <code>openstack-cinder-volume</code> service. If the volume is attached or detached without restarting the service, the operation might fail.</li> </ul>

Resource type	Contents
Host group for I/O data path	<p>Manual configuration:</p> <ul style="list-style-type: none"> <li>▪ Create a host group for the port that connects the controller node and compute nodes to the storage system. In a multipath configuration, create host groups for all connecting ports.</li> <li>▪ For a multipath configuration, the LDEV numbers and the connection order (LUN) must match within each host group of the target node. If they do not match, change each LDEV connection accordingly to match each LUN.</li> <li>▪ The host group must be named <code>HBSD-<i>&lt;target host WWPN&gt;</i></code> (for example, <code>HBSD-0123456789ABCDEF</code>).</li> <li>▪ Specify <code>HBSD-<i>&lt;target host WWPN&gt;</i></code> using the WWN of the smallest WWPN used for the connecting node.</li> <li>▪ Register the WWN of the connecting node in the newly created host group.</li> <li>▪ If the host groups for a controller node and compute node are created, reboot the nodes to recognize these paths. If a new compute node is added and the host group for the node is created, reboot is necessary for only this node.</li> </ul> <p>Automatic configuration:</p> <ul style="list-style-type: none"> <li>▪ Automatic creation of host groups requires the <code>hitachi_group_request</code> parameter to be <code>True</code>. In addition, to add LDEVs to a host group being created at the same time, Fibre Channel switches must be used to connect the storage and the node, and the Fibre Channel Zone Manager must be enabled.</li> <li>▪ Upon a cinder volume attach request, the driver automatically creates host groups on ports specified by the <code>hitachi_target_ports</code> parameter or the <code>hitachi_compute_target_ports</code> parameter if there is no host group that is connected to the VM instance. The host group name is <code>HBSD-<i>&lt;host WWPN&gt;</i></code>. The driver registers all host WWPNs with the created host group.</li> <li>▪ Automatic deletion of host groups requires the <code>hitachi_group_delete</code> parameter to be set to <code>True</code>.</li> </ul>

Resource type	Contents
Fibre Channel zoning	<p>Manual configuration:</p> <ul style="list-style-type: none"> <li>For Fibre Channel switches between a node and the storage device, manually configure zoning.</li> </ul> <p>Automatic configuration:</p> <ul style="list-style-type: none"> <li>When the driver attaches a volume to the target VM, Fibre Channel Zone Manager automatically creates zoning between the target node and the port used by the driver.</li> <li>Enable Fibre Channel Zone Manager and set the <code>hitachi_zoning_request</code> to <code>True</code>.</li> </ul>

## iSCSI connectivity

The following table describes iSCSI storage configuration requirements.

Resource type	Contents
Ports	<ul style="list-style-type: none"> <li>Enable port security for the ports used by the driver.</li> <li>Assign an IP address and a TCP port number to the port.</li> <li>If you change the port configuration used by the driver for connection, restart the <code>openstack-cinder-volume</code> service. If the volume is attached or detached without restarting the service, the operation might fail.</li> </ul>
iSCSI target for I/O data path	<p>Manual configuration:</p> <ul style="list-style-type: none"> <li>Create an iSCSI target for the port that connects the controller node and compute nodes to the storage system. In a multipath configuration, create iSCSI targets for all connecting ports.</li> <li>The iSCSI target must be named <code>HBSD-&lt;my_ip&gt;</code> (for example, <code>HBSD-10.20.30.40</code>). Use the same IP address for <code>my_ip</code> that you use for a cinder or nova compute service in each node.</li> <li>Register the Initiator IQN of the connecting node in the newly created iSCSI target.</li> <li>Register the Target IQN in the newly created iSCSI target. In a multipath configuration, register the same target IQN in all iSCSI targets connected to a node.</li> </ul>

Resource type	Contents
	<ul style="list-style-type: none"> <li>▪ In a multipath configuration, use the storage system management software to set 83 for the host mode option.</li> <li>▪ If CHAP authentication is used, register the CHAP user name and password with the iSCSI target. Use the same CHAP user and password for all iSCSI targets.</li> </ul> <p>Automatic configuration:</p> <ul style="list-style-type: none"> <li>▪ Automatic creation of iSCSI targets requires the <code>hitachi_group_request</code> parameter to be <code>True</code>.</li> <li>▪ Upon a cinder volume attach request, the driver automatically creates iSCSI targets on ports specified by the <code>hitachi_target_ports</code> parameter or the <code>hitachi_compute_target_ports</code> parameter if there is no iSCSI target that is connected to the VM instance. The target IQN of the created iSCSI target is <code>&lt;Initiator IQN&gt;.hbsd-target</code>. The driver registers the initiator IQN with the created iSCSI target.</li> <li>▪ Automatic deletion of iSCSI targets requires the <code>hitachi_group_delete</code> parameter to be <code>True</code>.</li> </ul> <p>Considerations for multipath configurations:</p> <ul style="list-style-type: none"> <li>▪ For a multipath configuration, the LDEV numbers and the connection order (LUN) must match within each iSCSI target of the target node. If they do not match, change each LDEV connection accordingly to match each LUN.</li> <li>▪ If the settings are automatic, the driver will use the smallest available iSCSI target number. Align the LUNs that are already being used for each port to force the LUNs created by the driver to match.</li> </ul>

## Configure Configuration Manager REST API server

Use the procedure below to configure the Configuration Manager REST API server.

### Procedure

1. Install the Configuration Manager REST API server.

For details, see *installing the REST API* in [Hitachi Command Suite Configuration Manager REST API Reference Guide](#).

2. Register information about the storage system to the Configuration Manager REST API server.

For details, see *Registering a storage system* in [Hitachi Command Suite Configuration Manager REST API Reference Guide](#).

```
# cat storage.json
{
  "model": "VSP F400",
  "serialNumber": "411111",
  "svplp": "10.197.74.6"
}
# curl -H "Accept:application/json" -H "Content-Type:application/json" -u USER_ID:PASSWORD -X POST --data-binary
@./storage.json https://192.0.2.100:23451/ConfigurationManager/v1/objects/storages
{
  "storageDeviceId": "834000411111",
  "model": "VSP F600",
  "serialNumber": "411111"
}
```

## Secure your storage system password

Your password file should be kept out of the file directories that are subject to data collection for logs. Follow the procedure below to keep your password from being shared with unauthorized users.

### Procedure

1. As a root user, create a password file using a text editor. For example:

**File:** `/opt/hitachi/hbsd/rest_password`

**Password:** `!gh8M59Wz#`

2. Confirm the password.

```
# cat /opt/hitachi/hbsd/rest_password
!gh8M59Wz#
```

3. Hide the password file from all users except the Cinder group.

```
# sudo chgrp cinder /opt/hitachi/hbsd/rest_password
# sudo chmod 640 /opt/hitachi/hbsd/rest_password
```

4. Specify the `hitachi_rest_password_path` parameter in the `cinder.conf` file (`/etc/cinder/cinder.conf`). For example,  
`hitachi_rest_password_path=/opt/hitachi/hbsd/rest_password.`



**Note:** Do not use the `hitachi_rest_password` parameter. The `hitachi_rest_password` and `hitachi_rest_password_path` parameters are mutually exclusive and using `hitachi_rest_password` will conflict with the password file path you have added to the `cinder.conf` file.

# Install Block Storage Driver for OpenStack

## Installation prerequisites

The installation prerequisites for Block Storage Driver for OpenStack are listed below.

- Verify that you have sufficient memory on the server. The physical memory size required by the software is: 1 MB x the number of backends x 2.
- Verify that you have sufficient disk space required to install the driver. The following table describes the required disk space.

Item	Size	Location
Block Storage Driver for OpenStack file	1 MB	/usr/share/pyshared/ hitachi-hbsd
hbsdgetinfo	1 MB	/opt/hitachi/hbsd/
Log files	100 MB	/var/log/cinder/

- Check the OpenStack package installation for any missing or invalid packages (see [Software \(on page 23\)](#)). Use the **rpm** command with the **-v** option specified (debsums for Ubuntu) to confirm that these packages are installed and are in a normal state. If a package is not installed or an invalid package is found, install the package again.

## Block Storage Driver for OpenStack installation for Red Hat and SUSE

Use the **rpm** command to install Block Storage Driver for OpenStack. You must log in as a superuser (root) on the controller node where you want to perform the installation. For details about how to use the **rpm** command, see the online documentation on the Linux website.

### Procedure

1. Use the **mount** command to mount the CD file system when installing from a CD:

```
# /bin/mount -r -o mode=0544 /dev/cdrom /media
```

2. Before installing the driver, stop the Cinder volume service.

For Red Hat:

```
# /usr/bin/systemctl stop openstack-cinder-volume
```

For SUSE:

```
# /sbin/service openstack-cinder-volume stop
```

- After the service is stopped, run the **rpm** command to install the driver. Install the appropriate RPM package for your OpenStack environment. The following table shows the Block Storage Driver for OpenStack RPM package for each supported OpenStack distribution.

RPM package name	RPM storage directory
hbsd-3.2.0-0_9.0.noarch.rpm	RPMS/noarch

An example of installing Block Storage Driver for OpenStack:

```
# /bin/rpm -ivh /media/RPMS/noarch/<RPM package name>
```

- After the installation is completed, use the **umount** command to unmount the CD.

```
# /bin/umount/media
```

## Block Storage Driver for OpenStack installation for Mirantis and Ubuntu

Use the **dpkg** command to install Block Storage Driver for OpenStack. You must log in as a superuser (root) on the controller node where you want to perform the installation. For details about how to use the **dpkg** command, see the Mirantis or Ubuntu online documentation.

### Procedure

- Use the **mount** command to mount the CD file system when installing from a CD:

```
# /bin/mount -r -o mode=0544 /dev/cdrom /media
```

- Before installing the driver, stop the cinder-volume service.

```
# /usr/sbin/service cinder-volume stop
```

- After the service is stopped, run the **dpkg** command to install the driver. The following table shows the DEB package for each supported OpenStack distribution.

DEB package name	DEB storage directory
hbsd_3.2.0-0-9.0_all.deb	DEBS/all

An example of installing Block Storage Driver for OpenStack:

```
# /usr/bin/dpkg -i /media/DEB/UBUNTU/all/<DEB package name>
```

4. After the installation is completed, use the `umount` command to unmount the CD.

```
# /bin/umount/media
```

## Initial setup

### Add a Block Storage Driver for OpenStack configuration

Normally, a Block Storage Driver for OpenStack configuration is added to the configuration file `/etc/cinder/cinder.conf` provided by an `openstack-cinder` package. However, some OpenStack configuration installers might automatically change the configurations of `cinder.conf` by running configuration management software such as Puppet. The following describes the procedure required in such situations.

#### Using Director (Red Hat OpenStack Platform)

A Puppet agent runs on the controller node when an OpenStack environment is built with the Director. The Puppet agent resets `cinder.conf` for the controller node and any configuration you have built in the driver will be lost. To avoid this, disable Puppet agent on all the controller nodes.

```
# puppet agent --disable
```

To configure the driver, edit the configuration file `/etc/cinder/cinder.conf` on all controller nodes.



**Note:** While the Puppet agent is being stopped, nodes cannot be added by the Director. For this reason, if you need to add nodes, first back up `cinder.conf` and run the Puppet agent, and then add nodes. When you have finished adding nodes, disable the Puppet agent and restore `cinder.conf` from the backup.

#### Using Crowbar (SUSE OpenStack Cloud)

A Chef agent runs on the controller node when an OpenStack environment is built with Crowbar. Chef resets `cinder.conf` for the controller node, and any configuration you have built in the driver will be lost. To resolve this issue, follow the procedure below to add your driver configuration to the **Add New Cinder Backend** page in the Crowbar WebGUI.

##### Procedure

1. Launch the WebGUI of Crowbar, and select **OpenStack** in the **Barclamps** menu.
2. Select **Edit** in Cinder.
3. Select **Other Driver** in the **Type of Volume** menu in the **Add new Cinder Backend** field. Click **Add Backend** to enter the name of the backend.

4. Enter the driver path in the **Driver** field and the parameters in the **Options** field for the backend you have added.
5. In the **Deployment** field, specify the controller node (only one selectable) in the **cinder-controller** field. And specify the backend(s) in the **cinder-volume** field.
6. Click **Apply** to save the configuration.

## Using FUEL (Mirantis OpenStack)

To configure Block Storage Driver for OpenStack using Mirantis OpenStack, edit the configuration file (`/etc/cinder/cinder.conf`) on the controller node.

## Using MAAS (Ubuntu OpenStack)

To configure the driver using Ubuntu, edit the configuration file (`/etc/cinder/cinder.conf`) on the controller node.

## Linking a volume type and a backend

For creating an environment with multiple backends, you can create a volume type and link it to a particular backend.

You can configure the backend specification (`volume_backend_name`) during backend setup by using the **cinder** command in the controller node where a Cinder client is installed.

```
# /usr/bin/cinder type-create <volume type name>
# /usr/bin/cinder type-key <volume type name> set
volume_backend_name=<volume backend name>
```

The following commands show an example of creating a volume type called `HBSD_SAMPLE1` and linking it to the backend `hbsd_backend1`.

```
# /usr/bin/cinder type-create HBSD_SAMPLE1
# /usr/bin/cinder type-key HBSD_SAMPLE1 set
volume_backend_name=hbsd_backend1
```

Use the **cinder** `extra-specs-list` command to check the volume type you created and the value registered for the `volume_backend_name` key.

```
# /usr/bin/cinder extra-specs-list
```

ID	Name	extra_specs
<Volume Type ID>	HBSD_SAMPLE1	{u'volume_backend_name': u'hbsd_backend1'}

## Edit cinder.conf

A driver configuration is added using the OpenStack configuration installer provided by the distribution in use (see [Add a Block Storage Driver for OpenStack configuration \(on page 39\)](#)). This topic describes how to edit the configuration file `/etc/cinder/cinder.conf` provided by the `openstack-cinder` package.

Specify the driver settings in the configuration file `/etc/cinder/cinder.conf`. You need to manually update the configuration file with values that reflect the latest storage configuration. Specify "*parameter=value*" pair per line in the following format:

```
parameter=value
```

Specify the driver-specific parameters and Cinder-provided parameters for each backend. An example Block Storage Driver for OpenStack configuration is shown below, followed by the description of each section of the file. For details about the parameters, see [Parameters \(on page 59\)](#).

```
# cinder.conf sample #
[DEFAULT]
: (Omitted)
enabled_backends=VSPG1000
logging_context_format_string=%(asctime)s.%(msecs)03d % (process)d %
(thread)s
%(levelname)s %(name)s [%(request_id)s %(user_identity)s] % (instance)s%
(message)s
: (Omitted)
[VSPG1000]
volume_driver=cinder.volume.drivers.hitachi.hbsd.hbsd_fc.HBSDFCDriver
volume_backend_name=hbsd_backend1
suppress_requests_ssl_warnings=True
hitachi_storage_id=800000054321
hitachi_pool=0
hitachi_rest_api_ip=192.0.2.100
hitachi_rest_user=user
hitachi_rest_password_path=/opt/hitachi/hbsd/rest_password
hitachi_target_ports=CL1-A,CL2-A
hitachi_compute_target_ports=CL1-B,CL2-B
```



### Note:

- If you want to share a port between multiple backends in a multipath configuration, specify the same port name for all the ports used by the backends. If the same port name is specified for only some of the backends, volume-connection operations might fail.
- If you use the Configuration Manager REST API server's default server authentication, set `suppress_requests_ssl_warnings=True`.
- If you use attach operations for multiple volumes, it is recommended that you set `rpc_response_timeout` to a larger value.

## Restart Cinder

To complete the configuration, use the **cinder** command to restart the cinder-volume service.

Run the following commands to restart the cinder-volume service.

- For Red Hat, use the **systemctl** command:

```
# /usr/bin/systemctl restart openstack-cinder-volume
```

- For SUSE, use the **service** command:

```
# /sbin/service openstack-cinder-volume restart
Currently stopped openstack-cinder-volume: [ OK ]
Currently starting openstack-cinder-volume: [ OK ]
```

- For Ubuntu and Mirantis, use the **service** command:

```
# /usr/sbin/service cinder-volume restart
Currently stopped cinder-volume: [ OK ]
Currently starting cinder-volume: [ OK ]
```

## Verify Block Storage Driver for OpenStack installation

This topic describes the methods that you can use to verify installation and configuration of Block Storage Driver for OpenStack.

## Procedure

1. After the Cinder service restarts, make sure that Block Storage Driver for OpenStack is available for use by verifying the following:

- The message MSGID0003-I is output to the following log file.

Red Hat OpenStack Platform: /var/log/cinder/volume.log

SUSE OpenStack Cloud, Mirantis OpenStack, and Ubuntu OpenStack: /var/log/cinder/cinder-volume.log

```
# /bin/grep MSGID0003-I /var/log/cinder/volume.log
2018-09-21 13:53:06.067 137596 WARNING
cinder.volume.drivers.hitachi.hbsd.hbsd_utils [req-6d5ebee0-8940-
43b0-b3d4-1d320c2ad447 - - - -] MSGID0003-I: The storage backend
can be used. (config_group: VSP_G1000)
```

- The state of the cinder-volume service of the backend(s) is up. This can be displayed by the **cinder service-list** command as shown in the following example. The backend(s) whose state is up can be used for volume operations. If the state is down, check the log file for relevant messages.

```
# /usr/bin/cinder service-list
```

Binary	Host	Zone	Status	State	Updated_at
cinder-backup	hostname.localdomain	nova	enabled	up	2014-07-07T12:31:10.000000
cinder-scheduler	hostname.localdomain	nova	enabled	up	2014-07-07T12:31:12.000000
cinder-volume	hostname.localdomain@VSPG1000	nova	enabled	up	2014-07-02T02:55:47.000000

2. Verify that the following volume operations can be performed from the Horizon portal:

- Create a volume
- Delete a volume
- Attach a volume
- Detach a volume
- Create a snapshot
- Delete a snapshot
- Create a volume from snapshot

If any of these volume operations fail, check the error messages output to the OpenStack Cinder log file.

## Update the Block Storage Driver for OpenStack

### Update the Block Storage Driver for OpenStack software for Red Hat and SUSE

Use the procedure described below to update the driver software for Red Hat and SUSE.

#### Procedure

1. Stop the cinder-volume service.

For Red Hat:

```
# /usr/bin/systemctl stop openstack-cinder-volume
```

For SUSE:

```
# /sbin/service openstack-cinder-volume stop
```

2. After the service has stopped, install a new version of the driver as shown below:

```
# /bin/rpm -Uvh /media/RPM-storage-directory/RPM-package-name
```

For the RPM package name and RPM storage name, see [Block Storage Driver for OpenStack installation for Red Hat and SUSE \(on page 37\)](#).

3. After updating the driver software, check the parameters in the `cinder.conf` file and update them as needed.

For details on each parameter, see [Parameters \(on page 59\)](#).

### Update the Block Storage Driver for OpenStack software for Mirantis and Ubuntu

Use the procedure described below to update the driver software for Mirantis and Ubuntu.

#### Procedure

1. Stop the cinder-volume service.

```
# /usr/sbin/service cinder-volume stop
```

2. After the service stops, run the `dpkg` command to install the driver.

For the DEB package name and DEB storage name, see [Block Storage Driver for OpenStack installation for Mirantis and Ubuntu \(on page 38\)](#).

3. After updating the driver software, check the parameters in the `cinder.conf` file and update them as needed.

For details on each parameter, see [Parameters \(on page 59\)](#).

## Uninstall Block Storage Driver for OpenStack

Follow the procedure below to uninstall the driver.

### Procedure

1. Stop the cinder-volume service.

- For Red Hat:

```
# /usr/bin/systemctl stop openstack-cinder-volume
```

- For SUSE:

```
# /sbin/service openstack-cinder-volume stop
```

- For Ubuntu and Mirantis:

```
# /usr/sbin/service cinder-volume stop
```

2. Uninstall the driver.

- For Red Hat and SUSE:

```
# /bin/rpm -e hbsd
```

- For Ubuntu and Mirantis:

```
# /usr/bin/dpkg --purge hbsd
```

## Live migration

The Cinder live migration capability allows you to migrate a VM to another host for hardware maintenance and other purposes without disrupting workloads. See online documentation such as *OpenStack Cloud Administrator Guide* for details about the live migration function on Nova components and the usage of the OpenStack configuration installer provided by the distribution in use.

When you perform live migration using Block Storage Driver for OpenStack, follow these guidelines:

- Configure DM-Multipath in compute node by editing the configuration file (for example, `/etc/multipath.conf`) and then restarting the multipath daemon. See [Configure multipathing \(on page 46\)](#).

- `user_friendly_names` is set to `"no"`
- `find_multipaths` is set to `"no"`

DM-Multipath is required for performing live migration for both single and multipath configurations.



**Note:** Volume migration finishes even if it fails to delete the LDEV of the original volume. In this case, delete it manually because the LDEV of the original volume remains in storage.

## Configure multipathing

Redundant I/O data paths to the storage device enable continuous operations when one of the paths fails. Device mapper multipathing (DM-Multipath) provides path redundancy in OpenStack as illustrated in the figure in [Connect nodes \(on page 27\)](#).

DM-Multipath creates and attaches a multi-path device (dm-X) to the VM.

The details of multipath configuration for controller and compute nodes are described below. See [Cinder-specific parameters \(on page 68\)](#) for the parameter details. In addition, see the Linux website for documentation on setting up DM-Multipath.

Controller nodes:

- Set `True` for the `use_multipath_for_image_xfer` parameter.
- Configure DM-Multipath for the port specified by the Block Storage Driver for OpenStack parameter `hitachi_target_ports` and `hitachi_compute_target_ports`.
- Start multipath daemon after configuring the DM-Multipath setting.

Compute nodes:

- Set `True` for the `volume_use_multipath` parameter. List this parameter in the `libvirt` section in the Nova configuration file.
- Start the multipath daemon after configuring the DM-Multipath setting.

**Note:**

- The recommended value for the DM-Multipath varies depending on the storage device. Refer to multipath configuration guidelines of your storage device.
- Configure the live-migration parameters to use live migration (see [Live migration \(on page 45\)](#)).
- Attach or detach volume operation of the volume may fail when one of the iSCSI paths fails. However, VMs that the volume is attached to can be used with the other path.

## Configure high availability

### High availability configuration overview

You can configure multiple controller nodes in a cluster to ensure high availability. If one node fails, the system fails over to another node to continue operations without any disruption to the workloads. Each service can select active-standby or active-active configuration with Pacemaker.

However, active-standby is the only controller-node fail-over configuration supported by Block Storage Driver for OpenStack.

### Pacemaker configurations for Cinder volumes

Block Storage Driver for OpenStack supports only active-standby configuration for Cinder volumes, and fencing actions reboot when the system fails over. To allow this, configure Pacemaker parameters for cinder volumes as described in the following table.

Parameter	Value
monitor	fencing
stop	fencing
start	fencing
start-delay	10s
clone-set	Delete this item

Configure the Pacemaker configuration using the **pcs** commands. You can reconfigure node behaviors after the node has been rebooted.

## Build high availability environment of controller node

Build high availability in a controller node by referring to the documentation of the high availability cluster software in use. After building the high availability configuration using Foreman, you can use the procedure below to configure Block Storage Driver for OpenStack.

### Procedure

1. Stop Puppet agent by disabling Puppet agent on all controller nodes.

```
# puppet agent -disable
```

2. To run Block Storage Driver for OpenStack backend, configure the pacemaker of the cinder volume by referring to Pacemaker configurations for Cinder volumes.
3. Remove the cinder volume from the monitoring list of Pacemaker temporarily.

```
# pcs resource disable cinder-volume
```

4. Configure the cinder-volume service and Block Storage Driver for OpenStack on all controller nodes. See the configuration values for the cinder-volume services in the following table.

Item	Content
my_ip parameter	Specify a unique IP address for each node.
host parameter	If you specify a common host name for all backends, specify this parameter in the DEFAULT section of the Cinder configuration file. Specify the same value (for example, <code>ha_cluster</code> ) for all controller nodes. This parameter is unnecessary when the <code>backend_host</code> parameter is specified.
backend_host parameter	If you specify a host name for each backend, specify this parameter in each backend section of the Cinder configuration file. Specify the same value (for example, <code>backend_ha_cluster</code> ) for all backends of the Controller node. If this parameter and the <code>host</code> parameter are specified, this parameter is used.
backend of Block Storage Driver for OpenStack	Specify the same value for each Controller node.

5. Configure the control paths to the storage device.

- Restart all the controller nodes.

```
# pcs cluster stop
# reboot
```

- After starting the controller node, verify that the backend storage of Block Storage Driver for OpenStack is running. For details, see [Verify Block Storage Driver for OpenStack installation \(on page 42\)](#). In addition, confirm that the cinder-volume service is running in an active-standby configuration by using the `pcs status` command.



**Note:** Once the Puppet agent is stopped, nodes cannot be added by Foreman. Back up the `cinder.conf` file and run Puppet agent and then add the node. After adding nodes, disable the Puppet agent and restore `cinder.conf` from the backup.

## Recoverable failures

When the system detects a storage control path failure that causes the Cinder volume service to abend, it switches the failed component to the normal one to continue the operations. Other types of failures might not be detected and as a result the Cinder volume service becomes unavailable.

When the failed system switches over, the node associated with the failed system will reboot. During the reboot, all services on the node will become unavailable. You can reconfigure the node behaviors after it has been rebooted. If you reconfigure the node to be added back to the cluster, the Active-Active services can be used as Active again.



### Note:

If the failed node is recovered and you want to switch the service back to the recovered node, make sure that there are no running snapshot volumes on the failover node by using the `cinder snapshot-list volume` command before you switch the node back.

## Handling high availability post-failover

When a controller node fails while storage operations are in progress, the operation target volumes might be left unprocessed in the storage. This may cause other operations that are involved with these resources to fail. Follow the procedure listed below to determine the correct actions.

### Procedure

- Check Pacemaker logs for the failover status and the time it has occurred.
- If the failover caused Cinder volume processing to stop, use the `cinder list` command to find the volumes or snapshot being processed.
- If the status of a volume is "creating" then go to step 4. Otherwise, perform the following steps:
  - Get the metadata of the volume or the snapshot by using the `cinder metadata-show` command and identify the LDEV number.

- b. Determine the storage operation from the volume status.
  - c. Based on the obtained LDEV number, in the storage system management software, ensure that the volume is restored to the status it was in before the operation.
  - d. Change the status for the corresponding entry on CinderDB to "available" using the **cinder** `reset-state` command.
  - e. Go to step 6.
4. Identify the incomplete volume processing from the file `volume.log` or `hbsd_debug.log` around the time when the failover occurred.
5. Check whether any LDEV is associated with the volume. If no LDEV is associated, go to the following step d. If an LDEV is associated, perform the following steps:
  - a. Obtain the pair information from the LDEV ID by using the management software. If a pair exists, delete it.
  - b. If the LDEV is mapped to a host group or an iSCSI target, disable the mapping.
  - c. Delete the LDEV by using the storage management software.
  - d. Change the state of the volume to "available" using the **cinder** `reset-state` command and delete the corresponding entry on CinderDB using the **cinder** `delete` command.
6. If there are any other volumes with incomplete processing, repeat steps 3 through 5.

## Chapter 4: Hitachi extended functions

This section provides details and examples for using the extended storage operation capabilities provided by Hitachi storage devices.

### Copy methods

When cloning volumes or creating snapshots, you can choose from one of the two copy methods, Thin Image (Clone) and Thin Image (Snapshot), provided by storage systems. When creating snapshots, the copy method is set to Thin Image (Snapshot). The following table describes which copy method is used under each setting. The copy method is selected by the `hitachi_default_copy_method` parameter and the `copy_method` metadata for the destination volume. For example, setting pattern 1 indicates that Thin Image (Clone) is used when you clone a volume if the `hitachi_default_copy_method` parameter is set to `FULL` and the `copy_method` metadata is not set.

Item		Value	Setting Pattern						
			1	2	3*	4*	5	6*	7
Settings	Operation	Create volume from volume (clone) or create volume from snapshot	T	T	T	T	T	T	F
		Create snapshot	F	F	F	F	F	F	T
	hitachi_default_copy_method parameter	FULL	T	T	T	F	F	F	F
		THIN	F	F	F	T	T	T	F
		FULL or THIN	F	F	F	F	F	F	T
	copy_method metadata	Not set	T	F	F	T	F	F	F
		FULL	F	T	F	F	T	F	F
		THIN	F	F	T	F	F	T	F
		FULL or THIN	F	F	F	F	F	F	T
	Selected copy method		T	T	F	F	T	F	F


Item	Value	Setting Pattern						
		1	2	3*	4*	5	6*	7
	Thin Image (Snapshot)	F	F	T	T	F	T	T
<p>Legend:</p> <ul style="list-style-type: none"> <li>▪ T: True</li> <li>▪ F: False</li> </ul> <p><b>Note:</b></p> <p>* Creating volumes by using Thin Image (Snapshot) is not recommended because you cannot delete source volumes or snapshots without deleting the destination volumes, and you cannot extend or unmanage source volumes, source snapshots, or destination volumes.</p>								

**Note:**

- Do not set or change metadata other than `copy_method`.
- You can use Thin Image (Snapshot) in cascade configurations. You can connect up to 64 levels.
- When using Thin Image (Snapshot) in a cascade configuration, you cannot delete any intermediary volumes. To delete an intermediary volume, you first must delete all volumes under the target volume.
- For the following storage system models, if you use Thin Image (Clone) to copy data to a volume of a different size, after asynchronous copy is performed, the volume is expanded. For this reason, processing might take longer than the time required to copy to a volume of the same size.
  - VSP F1500
  - VSP G1000
  - VSP F400, F600, F800
  - VSP G200, G400, G600, G800

The following describes the differences between the two types of processing:

- Cloning volumes of the same size: (volume creation process) + (initialization of asynchronous copy process)
  - Cloning volumes of different sizes: (volume creation process) + (initialization of asynchronous copy process) + (asynchronous copy completion wait time) + (volume capacity extension process)
- By using Thin Image (Clone), you can repeat the data copy operation for the target volume while it is being copied. You can repeat the operation up to three times. The fourth time will cause an error.



## Maximum number of copy pairs

The maximum number of Thin Image pairs that can be created for each LDEV assigned to a volume (or snapshot) is restricted as shown in the following table. If the number of pairs exceeds the maximum, copy operations will not function correctly.

Max. copy pairs per volume	Max. copy pairs per storage system
1,024	The number of ports used by the driver x 1,024

## Port assignment using extra specs

Defining particular ports in the Hitachi-supported extra spec `hbsd:target_ports` determines which of the ports specified by the `hitachi_target_ports` or the `hitachi_compute_target_ports` parameters are used to create LUN paths during volume attach operations for each volume type.

The following example shows how to use commands to specify ports in the extra specs. If you want to add a new port, specify a different volume type.

```
$ cinder type-create HUS-VM1
$ cinder type-key HUS-VM1 set volume_backend_name=HUS-VM1
$ cinder type-key HUS-VM1 set hbsd:target_ports="CL1-A, CL2-A"
$ cinder type-create HUS-VM2
$ cinder type-key HUS-VM2 set volume_backend_name=HUS-VM2
$ cinder type-key HUS-VM2 set hbsd:target_ports="CL3-A, CL4-A"
$ cinder extra-specs-list
```

ID	Name	extra_specs
b0d66cce-2766-43ef-868c-0f3b17f61111	HUS-VM1	{u'hbsd:target_ports': u'CL1-A, CL2-A', u'volume_backend_name': u'HUS-VM1'}
b0d66cce-2766-43ef-868c-0f3b17f62222	HUS-VM2	{u'hbsd:target_ports': u'CL3-A, CL4-A', u'volume_backend_name': u'HUS-VM2'}




**Note:** Use a comma to separate multiple ports.

## Port scheduler

You can use the port scheduler function to reduce the number of WWNs, which are storage system resource.

In Block Storage Driver for OpenStack, if host groups are created automatically, host groups are created for each compute node or VM (in an environment that has a WWN for each VM). If you do not use the port scheduler function, host groups are created and the same WWNs are registered in all of the ports that are specified for the parameter `hitachi_compute_target_ports` or for the parameter `hitachi_target_ports`. For Hitachi storage devices, a maximum of 255 host groups and 255 WWNs can be registered for one port. When volumes are attached, the upper limit on the number of WWNs that can be registered might be unexpectedly exceeded.


The figure below shows an example of automatically created host groups.



For the port scheduler function, when the cinder-volume service starts, the Fibre Channel Zone Manager obtains the WWNs of active compute nodes and of active VMs. When volumes are attached, the WWNs are registered in a round-robin procedure, in the same order as the order of ports specified for the parameter `hitachi_compute_target_ports` or for the parameter `hitachi_target_ports`.

If you want to use the port scheduler function, set the `hitachi_port_scheduler` parameter. For details about the parameter, see [Block Storage Driver for OpenStack specific parameters \(on page 59\)](#).

The figure below shows an example of host groups created from the port scheduler.

**Note:**

- Fibre Channel is supported. For details about ports, see [Fibre Channel connectivity \(on page 32\)](#).
- If a host group already exists in any of the ports specified for the parameter `hitachi_compute_target_ports` or for the parameter `hitachi_target_ports`, no new host group will be created on those ports.
- Restarting the cinder-volume service re-initializes the round robin scheduling determined by the `hitachi_compute_target_ports` parameter or the `hitachi_target_ports` parameter.
- The port scheduler function divides up the active WWNs from each fabric controller and registers them to each port. For this reason, the number of WWNs registered may vary from port to port.

## Data deduplication and compression

Deduplication and compression (dedupe/comp) is a method of improving storage utilization by data reduction. Once your storage administrator has enabled dedupe/comp for the DP pool, you can create or delete system data volumes for use with deduplication and compression.

For details, see *Capacity saving function: data deduplication and compression* in the *Provisioning Guide* for the applicable storage system, as listed in [Referenced documents \(on page 9\)](#).

## Enabling deduplication and compression

### Enabling dedupe/comp functionality

To use the dedupe/comp function, your storage administrator must first enable the dedupe/comp function for the DP pool. For details on how to enable this setting, see the description of pool management in the [Hitachi Command Suite Configuration Manager REST API Reference Guide](#).



#### Note:

Configure the virtualization-excess ratio to be unlimited. If you want to set some other value for the virtualization-excess ratio, keep in mind that the capacity of the system data volume is 40 TB.

## Creating a volume with dedupe/comp enabled

To create a volume with the dedupe/comp setting enabled, you need to enable dedupe/comp for the relevant volume type.

### Procedure

1. To enable the dedupe/comp setting, specify *deduplication\_compression* for *hbsd:capacity\_saving* in the extra specs for the volume type. The example below shows how to enable the dedupe/comp function for volume type *VSP-G1500-1*.

```
# cinder type-create VSP-G1500-1
# cinder type-key VSP-G1500-1 set hbsd:capacity_saving=deduplication_compression
# cinder extra-specs-list
```

ID	Name	extra_specs
fb994628-3983-4a1b-8b88-d1926a14a43d	VSP-G1500-1	{'hbsd:capacity_saving': 'deduplication_compression'}

2. When creating a volume of the volume type created in the previous step, you can create a volume with the dedupe/comp function enabled.

The example below shows how to create a volume (10 GB) with the dedupe/comp function enabled, where the volume type is *VSP-G1500-1*.

```
# cinder create --volume-type VSP-G1500-1 10
```

Property	Value
attachments	[]
availability_zone	nova
bootable	false
consistencygroup_id	None
created_at	2016-10-25T02:24:05.000000
description	None
encrypted	False
id	edeb50d8-d340-4e3a-924b-0feb6f2b948
metadata	{}
migration_status	None
multiattach	False
name	None
os-vol-host-attr:host	None
os-vol-mig-status-attr:migstat	None
os-vol-mig-status-attr:name_id	None
os-vol-tenant-attr:tenant_id	2afa8c77df6245b5939896a95b34f84c
replication_status	disabled
size	10
snapshot_id	None
source_vol_id	None
status	creating
updated_at	None
user_id	60361daadb8d4aee8034c541f5089323
volume_type	VSP-G1500-1

## Deleting a volume with dedupe/comp enabled

The `cinder delete` command finishes when the storage system starts the LDEV deletion process. The LDEV cannot be reused until the LDEV deletion process is completed on the storage system.

## Chapter 5: Parameters

This section provides syntax for both Block Storage Driver for OpenStack-specific parameters and the Cinder-specific parameters. See the example configuration file in [Edit cinder.conf \(on page 41\)](#).

### Block Storage Driver for OpenStack specific parameters

The table below describes parameters specific to Block Storage Driver for OpenStack, which are specified in the backend section of `cinder.conf`.

Parameter	Usage	Default value	Description
<code>hitachi_storage_id</code>	Required	None	Specifies the storage device ID (12 digits) registered on the REST API server.  Storage device ID: fixed value per device type (6 digits) + serial number (6 digits)  If the serial number has fewer than 6 digits, add zeroes (0) to the front of the serial number.
<code>hitachi_storage_cli</code>	Required	REST	If you specify <code>REST</code> , the Configuration Manager REST API is used for all storage-system operations.  If you are using a VSP F350, F370, F700, F900 or VSP G350, G370, G700, G900 storage system, specify <code>SIMPLE_REST</code> . API requests that get information in a simple format and those that return responses at a high speed are used when volumes are attached or when volumes are created (as clones or snapshots).
<code>hitachi_pool</code>	Required	None	Specifies the ID (integer) or the name of the DP pool that stores LDEVs for volumes (or snapshots). Do not use the DP pool specified for <code>hitachi_pool</code> for other purposes.

Parameter	Usage	Default value	Description
hitachi_thin_pool	Optional	None	If you use the TI pool for creating snapshots, specify the ID (integer) or the name of the TI pool that stores LDEVs for volumes or snapshots. If you omit this parameter, the snapshots created by using Thin Image (Snapshot) are stored in the pool specified for <code>hitachi_pool</code> .
hitachi_ldev_range	Optional	None	Specifies a range of usable LDEV numbers in the <code>&lt;integer-value-1&gt; - &lt;integer-value-2&gt;</code> format. The value of <code>&lt;integer-value-1&gt;</code> must be equal to or smaller than the value of <code>&lt;integer-value-2&gt;</code> . If no value is specified, one of the following ranges applies: (1) If no resource group is used, the entire range permitted by the storage system can be used, or (2) The entire range permitted in a resource group for the user specified by the <code>hitachi_rest_user</code> can be used. You can specify integer values by using a decimal format or colon-separated hexadecimal format ( <code>xx:yy:zz</code> ).
hitachi_rest_number	Optional	0	Specifies the number for identifying the Cinder driver instance. The value is used in names of storage resources (copy groups, device groups, and snapshots). Integer value (0-255).
hitachi_rest_user	Required	None	Specifies the user name used for authentication to access the storage device. If the driver manages multiple storage devices, use the same user name, password, resource group and permission for all storage systems.

Parameter	Usage	Default value	Description
hitachi_rest_password or hitachi_rest_password_path	Required	None	Specifies the password used for authentication to access the storage device. Only one of the parameters should be specified, not both. If neither parameter is specified, startup of the backend will fail. For security reasons, it is strongly recommended that you use the <code>hitachi_rest_password_path</code> parameter. For more information about how to secure the password, see <a href="#">Secure your storage system password (on page 36)</a> .
hitachi_rest_name_only_discovery	Optional	False	Sets a search restriction on host groups or iSCSI targets when attaching and detaching volumes. If <code>True</code> is specified, the driver searches only the host groups or the iSCSI targets that are named <code>HBSD-&lt;target host WWPN&gt;</code> or <code>HBSD-&lt;IP Address of the connecting host (my_ip)&gt;</code> , and ignores the rest. If host groups or iSCSI targets are created under different names, attaching and detaching volumes will result in an error.  If <code>False</code> is specified, the driver searches the rest if it does not find specific host groups or iSCSI targets that match these names. In this case, a search might take more time.
hitachi_target_ports	Optional	None	Specifies the controller port name to search host groups (iSCSI targets) when attaching volumes. Specify the port name in a format conforming to the storage system that uses it (for example, <code>VSP G1000: CL1-A</code> ). To use multipath connection, specify controller port names, separated by a comma (for example, <code>CL1-A, CL2-A</code> ). When attaching volumes to the Controller node, the controller port specified for this parameter is used. When attaching to the Compute node, the controller port specified for this parameter is used if <code>hitachi_compute_target_ports</code> is <code>None</code> (default).

Parameter	Usage	Default value	Description
			<p>When this parameter is not specified and <code>hitachi_compute_target_ports</code> as well as <code>hitachi_rest_pair_target_ports</code> are specified, the driver operates as the environment without the I/O data path of the Controller node.</p> <p>If you have a backend storage system for which <code>SIMPLE_REST</code> is specified for the <code>hitachi_storage_cli</code> parameter and a backend storage system for which a different value is specified for the parameter, do not set the same port number for those backend storage systems.</p>
<code>hitachi_compute_target_ports</code>	Optional	None	<p>Specifies the controller port name to search host groups (iSCSI targets) when attaching volumes to a compute node. Specify the port name in a format conforming to the storage system that uses it (for example, <code>VSP G1000: CL1-A</code>). To use the multipath connection, specify the controller port names separated by a comma. If None (default) is specified, the controller port specified by <code>hitachi_target_ports</code> is used.</p> <p>If you have a backend storage system for which <code>SIMPLE_REST</code> is specified for the <code>hitachi_storage_cli</code> parameter and a backend storage system for which a different value is specified for the parameter, do not set the same port number for those backend storage systems.</p>

Parameter	Usage	Default value	Description
<code>hitachi_rest_pair_target_ports</code>	Optional	None	This parameter is for an obsolete function and you do not need to specify this unless you omit the <code>hitachi_target_ports</code> parameter. If you omit the <code>hitachi_target_ports</code> parameter, specify the same value as the one specified by the <code>hitachi_compute_target_ports</code> parameter. Host groups or iSCSI targets named <code>HBSD-pair00</code> is created on the specified ports, but they are not actually used.
<code>hitachi_group_request</code>	Optional	False	Specifies <code>True</code> or <code>False</code> to determine whether a host group (iSCSI target) is created automatically if a host group (iSCSI target) corresponding to the connection target node does not exist for the port specified by the <code>hitachi_target_ports</code> or <code>hitachi_compute_target_ports</code> parameter. If <code>False</code> (default) is specified, the driver does not create the host group automatically.
<code>hitachi_group_delete</code>	Optional	False	Defines specifications for automatically deleting empty host groups or iSCSI targets assigned to the target ports specified by the <code>hitachi_target_ports</code> or <code>hitachi_compute_target_ports</code> parameter. Set <code>False</code> to not delete automatically. Set <code>True</code> to delete automatically. If you specify <code>True</code> , you must also specify <code>True</code> for the <code>hitachi_group_request</code> parameter. If the Fibre Channel Zone Manager is used (the <code>hitachi_zoning_request</code> parameter must be set to <code>True</code> ), Fibre Channel zones configured for the host groups or iSCSI targets will be deleted.

Parameter	Usage	Default value	Description
hitachi_zoning_request	Optional	False	Specify this parameter if you are using a Fibre Channel connection. Specifies <code>True</code> or <code>False</code> to determine whether Fibre Channel zoning between the storage system and connection target node is configured automatically by collaborating with Fibre Channel Zone Manager. To configure automatically, you need to enable Fibre Channel Zone Manager. See the online manual for the configuration of Fibre Channel Zone Manager. If <code>False</code> (default) is specified, Fibre Channel zoning is not configured regardless of the availability of Fibre Channel Zone Manager.
hitachi_use_chap_auth	Optional	None	Specify this parameter if you are using an iSCSI connection. When using CHAP authentication of the iSCSI targets, set this parameter to <code>True</code> . For details, see <i>CHAP authentication</i> in the <i>Provisioning Guide</i> for the applicable storage system, as listed in <a href="#">Referenced documents (on page 9)</a> .
hitachi_auth_user	Optional	None	Specify this parameter if you are using an iSCSI connection. Specifies the CHAP user name used for authentication of the iSCSI target. See the relevant user documentation.  If <code>True</code> is specified for the <code>hitachi_use_chap_auth</code> parameter, this parameter is required.
hitachi_auth_password	Optional	None	Specify this parameter if you are using an iSCSI connection. Specifies the password for the <code>hitachi_auth_user</code> setting. See the relevant user documentation.  If <code>True</code> is specified for the <code>hitachi_use_chap_auth</code> parameter, this parameter is required.

Parameter	Usage	Default value	Description
hitachi_auth_password_path	Optional	None	Specify this parameter if you are using an iSCSI connection. Specifies the file path that contains the password hint for hitachi_auth_user. Either the hitachi_auth_password or the hitachi_auth_password_path parameter should be specified if using CHAP authentication. Block Storage Driver for OpenStack returns an error if both parameters are specified. The file must be placed in a directory where the Cinder user or group can access but outside the directory in which the files are collected for troubleshooting purposes (for example, /opt/hitachi/hbsd/auth_password).
hitachi_default_copy_method	Optional	FULL	Specifies the default copy_method for copying volumes. You can specify FULL for Thin Image (Clone) or THIN for Thin Image (Snapshot). For details about this parameter, see <a href="#">Copy methods (on page 51)</a> .
hitachi_copy_speed	Optional	3	Specifies the copy speed for copying volumes by using Thin Image (Clone) functions. You can specify a value in the range from 1 to 15. If nothing is specified, 3 is set. Specify 1 or 2 to select slow copy speed. Specify 3 to select normal speed, and specify 4 or larger to specify high speed (prior).
hitachi_copy_check_interval	Optional	3	Specifies the interval (seconds) at which pair creation is confirmed during a volume copy. You can specify a value in the range from 1 to 600. If nothing is specified, 3 (seconds) is set.
hitachi_async_copy_check_interval	Optional	10	Specifies the interval (seconds) at which copy pair deletion is confirmed. You can specify a value in the range from 1 to 600. If nothing is specified, 10 (seconds) is set.

Parameter	Usage	Default value	Description
<code>hitachi_rest_disable_io_wait</code>	Optional	False	Specifies whether to enable the I/O check suppression option for a host group when the host group is created. If this parameter is set to <code>True</code> , before performing volume detach operations, make sure that no storage I/O operations are being performed. By setting this parameter to <code>True</code> , you can avoid the problem described in <a href="#">Volume detach operation fails (on page 79)</a> .
<code>hitachi_rest_api_ip</code>	Required	None	Specifies the REST API server hostname or IP address.
<code>hitachi_rest_api_port</code>	Optional	23451	Specifies the REST API server port number. For details about the REST API server port number, see the <a href="#">Hitachi Command Suite Configuration Manager REST API Reference Guide</a> .
<code>hitachi_rest_tcp_keepalive</code>	Optional	True	<code>True</code> : Use TCP keepalive functionality in the communication with the REST API server. With this setting, REST API server failures are detected in a short time. <code>False</code> : Do not use TCP keepalive functionality in the communication with the REST API server.
<code>hitachi_over_subscription</code>	Optional	False	Enables the over-subscription function for VSP F350, F370, F700, F900 and VSP G350, G370, G700, G900 storage systems.
<code>hitachi_server_auto_create</code>	Optional	True	Enables automatic connection between the attached volume and the server. If <code>True</code> is specified, the object is automatically created or updated every time a Compute node requests to connect to a volume. This parameter is enabled only if <code>SIMPLE_REST</code> is specified for the <code>hitachi_storage_cli</code> parameter.  If <code>False</code> is specified, also specify <code>False</code> for the <code>hitachi_server_auto_delete</code> parameter.

Parameter	Usage	Default value	Description
hitachi_server_auto_delete	Optional	False	Enables automatic disconnection of the server from the detached volume. If this parameter is set to <code>True</code> , the object is automatically deleted if no volumes are attached to the relevant host. This parameter is enabled only if <code>SIMPLE_REST</code> is specified for the <code>hitachi_storage_cli</code> parameter.
hitachi_port_scheduler	Optional	False	Specify this parameter to enable or disable the port scheduler function. If you specify <code>True</code> , when an attach request is received, the active WWNs that are obtained by Fibre Channel Zone Manager will be distributed and registered to the host groups of each port of the storage system. To use this function, specify <code>True</code> for the <code>hitachi_group_request</code> and <code>hitachi_rest_name_only_discovery</code> parameter. If you specify <code>False</code> for the <code>hitachi_rest_name_only_discovery</code> parameter, it will take a long time to attach volumes.
hitachi_discard_zero_page	Optional	True	Enables discarding of zero-data pages after a volume is copied or a snapshot is created by using the <code>dd</code> command. If this parameter is set to <code>True</code> , zero-data pages are discarded.
hitachi_host_mode_options	Optional	None	Specifies the host mode options for the host group or iSCSI target to be created. To set multiple host mode options, separate them by using commas. This parameter is enabled only if <code>True</code> is specified for the <code>hitachi_group_request</code> parameter.  For iSCSI targets, the host mode option 83 (Report iSCSI Full Portal List Mode) is automatically set regardless of this parameter.

Parameter	Usage	Default value	Description
			If <code>True</code> is specified for the <code>hitachi_rest_disable_io_wait</code> parameter, the host mode option 91 (Disable I/O wait for OpenStack Option) is automatically set regardless of this parameter.

## Cinder-specific parameters

### Default section

The table below describes details for the Cinder parameters set in the default section of the `cinder.conf` file. Only the parameters relevant to Block Storage Driver for OpenStack are described here.

Parameter	Usage	Default value	Description
<code>enabled_backends</code>	Optional	None	Specifies the backend definition section to be used. To specify multiple labels, separate them by a comma (for example, <code>VSP_G1000_1</code> , <code>VSP_G1000_2</code> ). Do not specify more than 32 backends for the <code>enabled_backends</code> parameter.*
<code>my_ip</code>	Optional	<code>127.0.0.1</code>	Specifies the IP address of the local host (of the management path). You must use a unique address that is not used in other nodes.
<code>logging_context_format_string</code>	Optional	See the default value given in Block Storage Driver for OpenStack log output format.	Specifies the output format of logs.

Parameter	Usage	Default value	Description
<code>rpc_response_timeout</code>	Optional	60	Specifies the timeout period for attach or detach processing on a VM. If attach or detach processing times out, the processing is restarted. This parameter is specified in the DEFAULT section on the controller node that the cinder-api is running. To reflect the configuration, restart the openstack-cinder-api service.
<code>host</code>	Optional	None	Specifies a common host name for all backends. In the high availability configuration for controller nodes, specify the same value (for example, <code>ha_cluster</code> ) for each controller node. This parameter is not required if the <code>backend_host</code> parameter is specified in the backend definition section.
<b>Note:</b> * A maximum of 32 backends supported by Block Storage Driver for OpenStack can be used concurrently.			

### Block Storage Driver for OpenStack log output format

For Block Storage Driver for OpenStack, add thread information after the process information in the default format for log analysis.

Default:

```
%(asctime)s.%(msecs)03d %(process)d %(levelname)s
%(name)s [%(request_id)s %(user_identity)s]
%(instance)s %(message)s
```

## Block Storage Driver for OpenStack:

```
% (asctime)s.% (msecs)03d % (process)d % (thread)s
% (levelname)s % (name)s [% (request_id)s % (user_identity)s]
% (instance)s % (message)s
```

**Backend definition section**

The table below describes details for the Cinder parameters set in the backend section of `cinder.conf`.

Name	Usage	Default value	Description
<code>volume_driver</code>	Required	None	Specifies the path of the driver to be used as follows:  To use the FC driver:  <code>cinder.volume.drivers.hitachi.hbsd.hbsd_fc.HBSDFCDriver</code>  To use the iSCSI driver:  <code>cinder.volume.drivers.hitachi.hbsd.hbsd_iscsi.HBSDISCSIDriver</code>  If no path is specified, startup of the backend will fail.
<code>volume_backend_name</code>	Optional	None	Specifies the name of the backend associated with the volume type.
<code>reserved_percentage</code>	Optional	0	Specifies the reserved area size for the back-end storage, using a value in the range from 0 to 100 (%). To provide no reserved area, specify 0 (default).

Name	Usage	Default value	Description
<code>use_multipath_for_image_xfer</code>	Optional	False	When the controller node and storage are connected via multipath, specify <code>True</code> or <code>False</code> to determine whether to set up a redundant configuration using a DM-Multipath in the controller node. To set up a redundant configuration, you must start the multipath daemon in advance. If you do not want to set up a redundant configuration, specify <code>False</code> (default).
<code>backend_host</code>	Optional	None	Specifies a host name for a target backend. In the high availability configuration for controller nodes, specify the same value (for example, <code>backend_ha_cluster</code> ) for each backend of the controller node. If this parameter and the host parameter are specified, this parameter is used.
<code>image_volume_cache_enabled</code>	Optional	False	This parameter is for Image Volume Cache, which cannot be used with Block Storage Driver for OpenStack. Set the value of this parameter to <code>False</code> .  If you want to quickly create a volume from an image, you can use the Volume-backed Image function.
<code>image_upload_use_cinder_backend</code>	Optional	False	This parameter is for the Volume-backed Image, which can be used if the parameter below is set to the value shown.  <code>hitachi_default_copy_method=FULL</code>

Name	Usage	Default value	Description
			To use this function, set the value of this parameter to <code>True</code> and set the parameter listed above to the value shown. To not use this function, set the value of the parameter to <code>False</code> .
<code>suppress_requests_ssl_warnings</code>	Optional	<code>False</code>	Suppress SSL certificate warnings.
<code>driver_ssl_cert_path</code>	Optional	<code>None</code>	Can be used to specify a non-default path to a <code>CA_BUNDLE</code> file or directory with certificates of trusted Certificate Authorities.
<code>driver_ssl_cert_verify</code>	Optional	<code>False</code>	If set to <code>True</code> , the SSL certificate of the REST API server will be enabled.
<code>max_over_subscription_ratio</code>	Optional	<code>20.0</code>	Specify the maximum over-subscription ratio of the pool of the storage system. The specified value must be <code>1.0</code> or more. This parameter is enabled only if <code>True</code> is specified for the <code>hitachi_over_subscription_ratio</code> parameter and the storage system model is VSP F350, F370, F700, F900, or VSP G350, G370, G700, G900.

---

## Chapter 6: Troubleshooting

When errors are returned or if you encounter problems, you can troubleshoot them. For errors that require additional investigation, see [Getting help \(on page 12\)](#).

### Check the version of Block Storage Driver for OpenStack

The first step in troubleshooting is to make sure you are running the desired version of Block Storage Driver for OpenStack that provides the Cinder functions you want to use.

If you encounter a problem, perform the following procedure to check the version of the driver and make sure the intended version is installed. If you are using an older version of the driver, update the software and perform the operation to confirm that the update has resolved the problem.

- For Red Hat and SUSE:

Run the following command:

```
# /bin/rpm -qi hbsd
```

- For Ubuntu and Mirantis:

Run the following command:

```
# /usr/bin/dpkg -s hbsd
```

### hbsdgetinfo command

#### Function

The command **hbsdgetinfo** collects data needed to investigate driver errors and outputs the data to `hbsdgetinfo-aaa.bbb.ccc.ddd-yyyyymmddhhmmss.tar.gz` (where `aaa.bbb.ccc.ddd` is the control node IP address and `yyyyymmddhhmmss` is the date and time of collection).

#### Format

```
/opt/hitachi/hbsd/sbin/hbsdgetinfo [-d directory] [-e cinder]
```

Parameter	Description
-d <i>directory</i>	Specify the directory to save the data to be collected. The directory name can be a maximum of 512 bytes long. The directory can be specified as an absolute or relative path. If you omit this parameter, the <code>/tmp</code> directory will be used.
-e <i>cinder</i>	Specify this parameter to remove data belonging to the Cinder group (data to be collected by the data collection command <code>cinder</code> ) from the collection target.

### Exit code

- 0: Success
- 1: Fail

### Collected data

Data in the common group is always collected. You can remove data in the Cinder group from the collection target by specifying the `-e` option.

Column	Collected data	Groups
Cinder (including Block Storage Driver for OpenStack) setting	All files below <code>/etc/cinder/</code>	Common
	<code>/etc/sudoers.d/cinder*</code>	Common
Cinder (including Block Storage Driver for OpenStack) log	All files below <code>/var/log/cinder/</code>	Common
Setting related to FC	<code>/etc/multipath.conf</code>	Common
	All files below <code>/etc/multipath.d/</code>	Common
System log	<code>/var/log/messages*</code>	Common
Setup of FC-related <sup>1</sup>	<code>/etc/multipath</code> directory	Common
Build date <sup>1</sup>	<code>/opt/hitachi/hbsd/build_date/*</code>	Common
<b>Note:</b> <b>1.</b> Ubuntu only.		

Column	Command	Output file name	Groups
Working status of Cinder	<b>cinder</b> absolute-limits	cinder_absolute-limits	Cinder
	<b>cinder</b> availability-zone-list	cinder_availability-zone-list	Cinder
	<b>cinder</b> backup-list	cinder_backup-list	Cinder
	<b>cinder</b> cgsnapshot-list	cinder_cgssnapshot-list	Cinder
	<b>cinder</b> consisgroup-list	cinder_consisgroup-list	Cinder
	<b>cinder</b> encryption-type-list	cinder_encryption-type-list	Cinder
	<b>cinder</b> extra-specs-list	cinder_extra-specs-list	Cinder
	<b>cinder</b> group-list	cinder_group-list	Cinder
	<b>cinder</b> group-snapshot-list	cinder_group-snapshot-list	Cinder
	<b>cinder</b> group-specs-list	cinder_group-specs-list	Cinder
	<b>cinder</b> group-type-list	cinder_group-type-list	Cinder
	<b>cinder</b> list	cinder_list	Cinder
	<b>cinder</b> qos-list	cinder_qos-list	Cinder
	<b>cinder</b> rate-limits	cinder_rate-limits	Cinder
	<b>cinder</b> service-list	cinder_service-list	Cinder
	<b>cinder</b> snapshot-list	cinder_snapshot-list	Cinder
	<b>cinder</b> transfer-list	cinder_transfer-list	Cinder

Column	Command	Output file name	Groups
	<b>cinder</b> type-list	cinder_type-list	Cinder
	<b>cinder</b> list-extensions	cinder_list-extensions	Cinder
	<b>pip</b> show cinder	pip_show_cinder	Cinder
Main status of All component of openstack	<b>openstack-status</b>	openstack-status	Common
Working status of hfcldd	<b>cat</b> /proc/scsi/hfcldd/*	cat_proc_scsi_hfcldd	Common
	<b>cat</b> /sys/class/scsi_host/host*/hfcldd_proc	cat_class_scsi_host_hfcldd_proc	Common
Working status of iSCSI	<b>iscsiadm</b> -m discovery -P 1	iscsiadm_m_discovery_P_1	Common
	<b>iscsiadm</b> -m session -P 3	iscsiadm_m_session_P_3	Common
Working status related to FC	<b>ls</b> -l /dev/disk/by-path	ls -l_dev_disk_by-path	Common
	<b>multipath</b> -ll	multipath_-ll	Common
	<b>cat</b> /sys/class/fc_host/host*/node_name	cat_sys_class_fc_host_node_name	Common
	<b>cat</b> /sys/class/fc_host/host*/port_state	cat_sys_class_fc_host_port_state	Common
System information	<b>uname</b> -a	uname_-a	Common
	<b>dmidecode</b>	dmidecode	Common
	<b>rpm</b> -qa <sup>1</sup>	rpm_-qa	Common

Column	Command	Output file name	Groups
	<b>rpm</b> -qi openstack-cinder <sup>1</sup>	rpm_ qi_openstack- cinder	Common
	<b>rpm</b> -qi hbsd <sup>1</sup>	rpm_-qi_hbsd	Common
	<b>rpm</b> -V python-cinder <sup>1,4</sup>	rpm -V python-cinder	Common
	<b>rpm</b> -V hbsd <sup>1,4</sup>	rpm -V hbsd <sup>4</sup>	Common
	<b>dpkg</b> -l <sup>2</sup>	dpkg_l	Common
	<b>dpkg</b> -s cinder-volume <sup>2</sup>	dpkg_s_cinder- volume	Common
	<b>dpkg</b> -s hbsd <sup>2</sup>	dpkg_s_hbsd	Common
	<b>ifconfig</b> -a	ifconfig_-a	Common
	<b>ethtool</b> _all <sup>3</sup>	ethtool_all	Common
System log	<b>journalctl</b>	journalctl	Common
<b>Notes:</b> <ol style="list-style-type: none"> <li>1. Red Hat, SUSE only.</li> <li>2. Ubuntu, Mirantis only.</li> <li>3. Script that collects <b>ethtool</b> information about all network interfaces in a system.</li> <li>4. The output format is <code>SM5DLUGT c &lt;file&gt;</code>. See the <b>rpm</b> online documentation for more details about the output format.</li> </ol>			

### Example

The following example shows how to use the command **hbsdgetinfo** to collect data.

```
# /opt/hitachi/hbsd/sbin/hbsdgetinfo
```

### Output example

The command **hbsdgetinfo** outputs as follows:

```
# /opt/hitachi/hbsd/sbin/hbsdgetinfo
hbsdgetinfo command started.
creating directory ... succeeded.
copying "/etc/cinder" ... succeeded.
copying "/etc/sudoers.d/cinder" ... succeeded.
copying "/var/log/cinder" ... succeeded.
: (Omitted)
```

```

executing "/usr/bin/cinder transfer-list" ... succeeded.
executing "/usr/bin/cinder type-list" ... succeeded.
executing "/usr/bin/cinder list-extensions" ... succeeded.
archiving files ... succeeded.
output to "/tmp/hbsdgetinfo-aaa.bbb.ccc.ddd-yyyymmddhhmmss.tar.gz"
hbsdgetinfo command completed successfully.

```

**Note:**

- The data that can be collected varies depending on the environment. If data collection fails, the command outputs error messages.
- The command outputs the message "hbsdgetinfo command completed successfully" to confirm successful completion of the command.
- To collect the data for the Cinder group, Keystone certification for the administrator user must be kept in the environment variables. To change settings for the environment variables, use the **env** command. If that is not possible, specify the **-e cinder** option and delete the Cinder group data from the output.

## Configuration Manager logs

If error messages starting with **KART-** are output to `/var/log/cinder/volume.log` and processing ends due to an error, Configuration Manager REST API log files might be required to investigate the problem.

For details on getting the logs, see *Collecting maintenance information about the REST API* in the [Hitachi Command Suite Configuration Manager REST API Reference Guide](#).

## Openstack-cinder-volume service does not start

If an error message for Block Storage Driver for OpenStack is output to `/var/log/cinder/volume.log`, see *Messages* to troubleshoot the problem.

If no error message is output for Block Storage Driver for OpenStack, a Cinder error message might be output to `syslog`.

## Volume (snapshot) cannot be created

Check for an error message in `volume.log`, and see [Messages \(on page 81\)](#) to troubleshoot problem.

## Volume (snapshot) cannot be attached

For error messages of Block Storage Driver for OpenStack in `volume.log`, see [Messages \(on page 81\)](#) to troubleshoot the problem.

## Volume operations fail in a multi-controller node environment

Verify that your OpenStack configuration is valid. Refer to [Supported configurations for Block Storage Driver for OpenStack \(on page 25\)](#).

## Volume attach and detach operations fail

Volume attach and detach operations might fail when multiple volume operations are performed concurrently. This can be caused by time outs that occur during the processing of the Cinder requests in the backends.

You can increase the timeout threshold for all the nodes by modifying the `rpc_response_timeout` parameter to `3600` in the `nova.conf` (`/etc/nova/nova.conf`) and the `cinder.conf` file (`/etc/cinder/cinder.conf`).



**Note:** Changing the value of the `rpc_response_timeout` parameter to a larger value may increase the time needed to complete processing if an error occurs during attach or detach operations.

## Volume detach operation fails

If you are using a software that detaches volumes in which no data is written, when you perform a volume detach operation, the target volume might have already been detached. In such cases, the volume detach operation fails because of a timeout error. To prevent this from occurring, set the I/O check suppression option (host mode option `91`) for the host group. If the `hitachi_group_request` parameter is set to `True`, and if new host groups are created automatically, specify this option by setting the `hitachi_rest_disable_io_wait` parameter to `True`.

If setting host groups or iSCSI targets for manual configuration, use the storage system management software to set `91` for the host mode option. For details on setting the host mode option, see the [Hitachi Command Suite Configuration Manager REST API Reference Guide](#).

## Volume attach performance issues after HBA replacement

Replacing a host bus adapter (HBA) in a multipath configuration can impact processing of volume attach requests in backend storage devices.

Make sure that the host group for the HBA has been updated after the replacement. If you have not already updated the host group name, with Storage Navigator, change the name to "HBSD-xxx" where xxx is the smallest WWPN number available for the server.

## Volume deletion causes error status

When deleting many volumes in one operation, some of the volumes may result in an *error\_deleting* status. If this happens, enter the `cinder reset-state` command. Verify volume status has returned to *available*, then retry deleting the volume(s).

## Contacting Hitachi Vantara Corporation customer support

If you need to contact Hitachi Vantara customer support, provide as much information about the problem as possible. Collect the files below and provide them along with the actions you have taken to resolve the problem.

- Use the `sosreport` (Red Hat, Ubuntu, Mirantis) or `supportconfig` (SUSE) command to collect data on all nodes.
- Use the `hbsdgetinfo` command to collect data on all controller nodes.
- Copies of the operation logs of high availability cluster software that collect data on the controller node in the high availability cluster. For example, `/var/log/pacemaker`.

## Chapter 7: Messages

### Message output format

This topic describes the format of messages that are output to the `volume.log` file.

The following is Block Storage Driver for OpenStack message format:

```
yyyy-mm-dd hh:mm:ss.fff PID loglevel filepath [request_id user tenant]  
message
```

Where:

- *yyyy-mm-dd hh:mm:ss.fff*: Date and time of output
- *PID*: Process ID
- *loglevel*: Log level
- *filepath*: File path of the output source
- *request\_id*: Request ID
- *user*: User ID
- *tenant*: Tenant ID
- *message*: Message content

The actual message content (indicated by *MSGID0000-t* in the message format above) is output as follow:

```
MSGIDn1n2n3n4-t: Message text
```

Where:

- *MSGID*: Indicates that the message is a driver message
- *n1n2n3n4*: The serial number of the message
- *t*: The message type

The message type indicates the operation corresponding to the message. The message types are as follows:

Type	Description
E	Error message indicating that processing cannot continue due to a driver error or an incorrectly specified option.

Type	Description
W	Warning message indicating that a driver error occurred or that an option was incorrectly specified, but that processing will continue.
I	Message providing additional information about processing. Messages that are neither error messages nor warning messages.

## List of messages

Message ID	Message text	Driver status	Required actions
0000-I	The method <i>&lt;method name&gt;</i> was called. (config_group: <i>&lt;backend definition name&gt;</i> )	Continues processing the request.	None.
0001-I	The parameter of the storage backend. (config_group: <i>&lt;backend definition name&gt;</i> )	Continues processing the request.	None.
0002-I	The method <i>&lt;method name&gt;</i> completed successfully. (config_group: <i>&lt;backend definition name&gt;</i> )	Continues processing the request.	None.
0003-I	The storage backend can be used. (config_group: <i>&lt;backend definition name&gt;</i> )	Continues processing the request.	None.
0300-W	Failed to configure the internal logging. (ret: <i>&lt;return value&gt;</i> , stderr: <i>&lt;standard error output&gt;</i> ).	Continues processing the request.	Verify that the user has sufficient permission for the directory.
0301-W	A LUN (HLUN) was not found. (LDEV: <i>&lt;LDEV number&gt;</i> )	Continues processing the request.	None.
0302-W	Failed to specify a logical device for the volume <i>&lt;volume ID&gt;</i> to be unmapped.	Continues processing the request.	None.
0303-W	An iSCSI CHAP user could not be deleted. (username: <i>&lt;CHAP user name&gt;</i> )	Continues processing the request.	If the CHAP user is no longer needed, delete it using the storage management software.

Message ID	Message text	Driver status	Required actions
0304-W	Failed to specify a logical device to be deleted. (method: <i>&lt;method name&gt;</i> , id: <i>&lt;volume ID   snapshot ID&gt;</i> )	Continues processing the request.	Make sure that the logical devices do not exist for unnecessary volumes.
0305-W	The logical device for specified <i>&lt;volume   snapshot&gt;</i> <i>&lt;volume ID   snapshot ID&gt;</i> was already deleted.	Continues processing the request.	Make sure that no invalid volumes or snapshots exist.
0306-W	A host group could not be deleted. (port: <i>&lt;port name&gt;</i> , gid: <i>&lt;group ID&gt;</i> )	Continues processing the request.	Take the actions specified in the previous message.
0308-W	A host group could not be added. (port: <i>&lt;port name&gt;</i> )	Continues processing the request for other ports.	Take the actions specified in the previous message.
0309-W	An iSCSI target could not be added. (port: <i>&lt;port name&gt;</i> )	Continues processing the request for other ports.	Take the actions specified in the previous message.
0310-W	Failed to unmap a logical device. (LDEV: <i>&lt;LDEV number&gt;</i> )	Continues processing the request for other ports.	Make sure that the logical devices do not exist for unnecessary volumes.
0311-W	A free LUN (HLUN) was not found. Add a different host group. (LDEV: <i>&lt;LDEV number&gt;</i> )	Continues processing the request.	None.
0312-W	Failed to get a storage resource. The system will attempt to get the storage resource again. (resource: <i>&lt;resource&gt;</i> )	Continues processing the request.	None.
0313-W	Failed to delete a logical device. (LDEV: <i>&lt;LDEV number&gt;</i> )	Continues processing the request.	Make sure that the logical devices do not exist for unnecessary volumes or snapshots.

Message ID	Message text	Driver status	Required actions
0314-W	Failed to map a logical device. (LDEV: <LDEV>, LUN: <LUN number>, port: <port name>, id: <group ID>)	Continues processing the request for the other host groups (iSCSI targets).	Take the actions specified in the previous message.
0315-W	Failed to perform a zero-page reclamation. (LDEV: <LDEV number>)	Continues processing the request.	None.
0317-W	Failed to assign the WWN. (port: <port name>, gid: <group ID>, wwn: <WWN>)	Continues processing the request for the other ports.	Take the actions specified in the previous message.
0318-W	Failed to copy meta data of destination volume <volume ID> to source volume <volume>. (reason: <detailed message>)	Continues processing the request.	None.
0319-W	The logical device does not exist in the storage system. (LDEV: <LDEV>)	Continues processing the request.	None.
0321-W	Failed to perform user authentication of the REST API server. (user: <user>)	Continues processing the request.	Verify user authentication information. Enter the correct values and retry the operation.
0324-W	Failed to delete full copy pair. (P-VOL: <LDEV number>, S-VOL: <LDEV number>)	Continues processing the request.	Take the actions specified in the previous message.
0325-W	Failed to delete thin copy pair. (P-VOL: <LDEV number>, S-VOL: <LDEV number>)	Continues processing the request.	Take the actions specified in the previous message.
0326-W	Failed to change the status of full copy pair. (P-VOL: <LDEV number>, S-VOL: <LDEV number>)	Continues processing the request.	Take the actions specified in the previous message.

Message ID	Message text	Driver status	Required actions
0329-W	Failed to detach the logical device. (LDEV: <LDEV number>, reason: <detailed message>)	Continues processing the request for the other ports.	Take the actions specified in the previous message.
0330-W	The port name specified for the extra spec key "hbsd:target_ports" of the volume type is not specified for the hitachi_target_ports or hitachi_compute_target_ports parameter in cinder.conf. (port: <port>, volume type: <volume type>)	Continues processing the request.	Correct the port name for the extra spec key hbsd:target_ports.
0331-W	Volume copy to a larger volume started. This process waits until all data is copied to the destination volume, and therefore it may take a long time before the destination volume becomes available. Consider copying to a volume with the same size to save time because it performs data copy in the background and therefore ends much faster. (source <volume   snapshot>: <volume-ID   snapshot-ID>, destination volume: <volume-ID>, source size: <source-size>, destination size: <destination-size>)	Continues processing the request.	Include the time required for data copying to the estimated time until the copy destination volume can be used. For faster subsequent copying of the volume, set the source volume and the destination volume to the same size.
0332-W	Failed to change a volume type. The storage system does not support deduplication, or deduplication is not enabled for the pool. (pool: <pool/>)	Continues processing the request using standard Cinder functions.	Check if the storage system supports deduplication. If it does, enable it, and then retry the operation.

Message ID	Message text	Driver status	Required actions
0333-W	Retrying the volume will be performed using migration because the specified volume is being rehydrated. This process may take a long time depending on the data size. (volume: <volume-ID>, volume type: <volume type>)	Continues processing the request using standard Cinder functions.	To change volume type quickly, do not change volume types that enable the dedupe/ compression function on volumes that just had the function disabled.
0334-W	Retrying the volume will be performed using migration because inconsistency was found in the deduplication system data volume. This process may take a long time depending on the data size. (volume: <volume-ID>, volume type: <volume type>)	Continues processing the request using standard Cinder functions.	To resolve the inconsistency in the system data volume, see your system administrator.
0335-W	Failed to create the host group because the host group maximum of the port is exceeded. (port: <port>)	Continues processing by using another port.	Check whether the port has any unnecessary host groups, and then delete those host groups.
0336-W	Failed to add the wwns to the host group port because the the WWN maximum of the port is exceeded. (port: <port>, WWN: <WWN>)	Continues processing by using another port.	Check whether the port has any unnecessary WWNs, and if it does, cancel the assignment of those WWNs.
0600-E	The Command <command> failed. (ret: <return value>, stdout:<standard output>, stderr:<standard error output>)	Stopped processing the request.	Remove the cause of the error by following the message output by the <b>external</b> command.
0336-W	Failed to add the wwns to the host group port because the the WWN maximum of the port is exceeded. (port: <port>, WWN: <WWN>)	Continues processing by using another port.	Check whether the port has any unnecessary WWNs, and then cancel the assignment of those WWNs.

Message ID	Message text	Driver status	Required actions
0601-E	A parameter is invalid. ( <i>&lt;parameter name   detailed message&gt;</i> )	Stopped processing the request.	Check and, if necessary, revise the specified parameter values, and then try the operation again with the correct values specified.
0602-E	A parameter value is invalid. ( <i>&lt;meta data name&gt;</i> )	Stopped processing the request.	Check and, if necessary, revise the specified parameter values, and then try the operation again with the correct values specified.
0603-E	Failed to acquire a resource lock. (serial: <i>&lt;serial number&gt;</i> , inst: <i>&lt;HORCM instance number&gt;</i> , ret: <i>&lt;return value&gt;</i> , stderr: <i>&lt;standard error output&gt;</i> )	Stopped processing the request.	Remove the cause of the error by following the message output by the <b>external</b> command.
0606-E	The snapshot <i>&lt;snapshot ID&gt;</i> cannot be deleted, because a read-only volume for the snapshot exists.	Stopped processing the request.	Make sure the snapshot operation target is correct. Alternatively, delete the target snapshot after deleting read-only volume related to the target snapshot.
0610-E	The status change of full copy pair could not be completed. (S-VOL: <i>&lt;LDEV number&gt;</i> )	Stopped processing the request.	Take the actions specified in the previous message.
0611-E	The status change of thin copy pair could not be completed. (S-VOL: <i>&lt;LDEV number&gt;</i> )	Stopped processing the request.	Take the actions specified in the previous message.
0612-E	The source logical device to be replicated does not exist in the storage system. (LDEV: <i>&lt;LDEV number&gt;</i> )	Stopped processing the request.	Specify the correct volume and retry the operation.

Message ID	Message text	Driver status	Required actions
0613-E	The volume <volume ID> to be extended was not found.	Stopped processing the request.	Specify the correct volume and retry the operation.
0614-E	No WWN is assigned. (port: <port name>, gid: <group ID>)	Stopped processing the request.	Take the actions specified in the previous message.
0615-E	A pair could not be created. The maximum number of pair is exceeded. (copy method: <copy-method name>, P-VOL: <LDEV number>)	Stopped processing the request.	If FULL is specified, wait for copying to finish, and then try the operation again. If THIN is specified, delete the unnecessary pairs, and then try the operation again.
0616-E	A pair cannot be deleted. (P-VOL: <LDEV number>, S-VOL: <LDEV number>(<pair status>) [, <LDEV number>(<pair status>)...])	Stopped processing the request.	Wait until the pair can be deleted, and then try the operation again. For Thin Image (Snapshot), you cannot delete only the P-VOL. You must first delete the S-VOL. If the pair status is PSUE, resolve the issue on the storage system, and then retry the operation.
0617-E	Failed to create a volume from <volume   snapshot>. The size of the new volume must be equal to or greater than the size of the original <volume   snapshot>. (new volume: <volume-ID>)	Stopped processing the request.	Set the size of the destination volume equal to or greater than the size of the original volume or snapshot.

Message ID	Message text	Driver status	Required actions
0618-E	The volume <volume-ID> could not be extended. The volume type must be Normal and the volume must not be an S-VOL in a cascade pair.	Stopped processing the request.	Verify the target volume is correct. If the type metadata is <code>Normal</code> , after the copy operation completes and the pair is deleted, retry the operation. If otherwise, since the volume cannot be extended, set the <code>copy_method</code> metadata to <code>FULL</code> , and then clone the volume. Extend and use this newly created volume.
0619-E	The volume <volume ID> to be mapped was not found.	Stopped processing the request.	Specify the correct volume, and then try the operation again. If the volume is no longer needed, delete the volume.
0620-E	Failed to provide information about a pool. (pool: <pool>)	Stopped processing the request.	Take the actions specified in the previous message.
0621-E	Failed to create a volume from <volume   snapshot>. The size of the new volume must be equal to the size of the original <volume   snapshot> when the new volume is created by Thin copy. (new volume: <volume-ID>)	Stopped processing the request.	Set the size of the destination volume equal to the size of the original volume or snapshot.
0624-E	HBSD has stopped processing the requests.	Stopped processing the request.	Specify the correct copy-source volume, and then try the operation again.
0631-E	Failed to create a file. (file: <file name>, error: <error number>, strerror: <error message>)	Stopped processing the request.	Check that the user has sufficient permission to perform the action on the directory.

Message ID	Message text	Driver status	Required actions
0633-E	Permission denied.	Stopped processing the request.	Check that the user has sufficient permission to perform the action on the file.
0634-E	Failed to attach the logical device. (LDEV: <LDEV number>, reason: <detailed message>)	Stopped processing the request.	Take the actions specified in the previous message.
0636-E	Failed to add the logical device.	Stopped processing the request.	Take the actions specified in the previous message.
0638-E	Failed to add the pair target.	Stopped processing the request.	Take the actions specified in the previous message.
0639-E	Failed to map a logical device to any pair targets. (LDEV: <LDEV number>)	Stopped processing the request.	Take the actions specified in the previous message.
0640-E	A pool could not be found. (pool: <pool/>)	Stopped processing the request.	Check and, if necessary, revise the parameter, and then restart the service.
0643-E	The iSCSI CHAP user <CHAP user name> does not exist.	Stopped processing the request.	Create the specified CHAP user. Alternatively, enable the parameter <code>hitachi_add_chap_user</code> to enable automatic creation of a CHAP user when creating an iSCSI target.
0648-E	There are no resources available for use. (resource: <resource>)	Stopped processing the request.	Check and, if necessary, revise the storage device settings and parameter settings to secure the target resources.

Message ID	Message text	Driver status	Required actions
0649-E	The host group or iSCSI target was not found.	Stopped processing the request.	Create the host group or iSCSI target. Alternatively, if you are using iSCSI, enable the parameter <code>hitachi_group_request</code> to enable automatic creation of an iSCSI target.
0650-E	The resource <i>&lt;resource&gt;</i> was not found.	Stopped processing the request.	Check the setting for the target resources.
0651-E	The IP Address was not found.	Stopped processing requests.	Make sure an IP address has been set for the storage device iSCSI port.
0652-E	Failed to delete a logical device. (LDEV: <i>&lt;LDEV number&gt;</i> )	Stopped processing the request.	Take the actions specified in the previous message.
0653-E	The creation of a logical device could not be completed. (LDEV: <i>&lt;LDEV number&gt;</i> )	Stopped processing the request.	Take the actions specified in the previous message.
0654-E	A volume status is invalid. (status: <i>&lt;status&gt;</i> )	Stopped processing the request.	Make sure the operation target volume is correct. Alternatively, wait until the status of the target volume becomes Available, and then try the operation again.
0655-E	A snapshot status is invalid. (status: <i>&lt;status&gt;</i> )	Stopped processing the request.	Make sure the snapshot operation target is correct. Alternatively, wait until the status of the target snapshot becomes Available, and then try the operation again.

Message ID	Message text	Driver status	Required actions
0656-E	<p>The volume &lt;volume ID&gt; could not be restored. (reason: &lt;detailed message&gt;)</p> <ol style="list-style-type: none"> <li>1. Invalid input:&lt;volume ID   snapshot ID&gt;</li> <li>2. Status of target volume &lt;volume ID&gt; is not "available":&lt;status of volume&gt;</li> <li>3. Status of source volume &lt;volume ID   snapshot ID&gt; is not "available":&lt;status of volume&gt;</li> </ol>	Stopped processing the request.	Make sure that the status and metadata for the specified volume are correct.
0657-E	A read-only volume cannot be created from the snapshot <snapshot ID>. A read-only volume already exists.	Stopped processing the request.	Make sure that the specified snapshot is correct.
0658-E	A new volume cannot be created from the snapshot <snapshot ID>. A read-only volume of the snapshot is attached.	Stopped processing the request.	Make sure that the specified snapshot is correct. Alternatively, detach the read-only volume from the instance before creating a new volume from the specified snapshot. After the new volume is created, reattach the read-only volume.
0659-E	A host group is invalid. (host group: <host group name>)	Stopped processing the request.	Create a host group.
0660-E	The specified <volume   snapshot> <volume ID   snapshot ID> is busy.	Stopped processing the request.	Make sure that the specified volume or snapshot is correct. Alternatively, wait for the other processing to finish, and then try the operation again.

Message ID	Message text	Driver status	Required actions
0700-E	No valid value is specified for "storage_id". A valid value must be specified for "storage_id" to manage the volume.	Stopped processing the request.	Make sure that the storage identifier information or the command is correct, and then try the operation again.
0701-E	No valid value is specified for "ldev". A valid value must be specified for "ldev" to manage	Stopped processing the request.	Make sure that the LDEV information or the command is correct and retry the operation.
0702-E	Failed to manage the specified LDEV (<LDEV number>). The LDEV must be an unpaired DP-VOL <volume type>.	Stopped processing the request.	Make sure that the target LDEV information is correct. Alternatively, if the target LDEV has a pair, delete the pair and retry the operation. The driver does not manage LDEVs that are not DP-VOL. Create a DP-VOL, copy the data from the LDEV, and then retry the operation.
0703-E	Failed to manage the specified LDEV (<LDEV number>). The LDEV size must be expressed in gigabytes.	Stopped processing the request.	Make sure that the target LDEV information is correct. Extend the LDEV so that it is expressed in gigabytes, and then retry the operation.
0704-E	Failed to manage the specified LDEV (<LDEV number>). The LDEV must not be mapped.	Stopped processing the request.	Make sure that the target LDEV information is correct. Unmap the LDEV and try the operation.
0705-E	Failed to manage the specified LDEV (<LDEV number>). The LDEV must not be mapped.	Stopped processing the request.	Make sure the target LDEV information is correct. Clone the volume and retry the operation.

Message ID	Message text	Driver status	Required actions
0706-E	Failed to unmanage volume <volume ID>. The volume type must be <i>Normal</i> and the volume must not be an S-VOL in a cascade pair.	Stopped processing the request.	Verify the target volume is correct. If the type metadata is <i>Normal</i> , retry the operation after copy completes and the pair is deleted. If otherwise, since the volume cannot be removed from Cinder management, set the <code>copy_method</code> metadata to <code>FULL</code> , and then clone the volume. Remove the newly created volume from Cinder management.
0707-E	No valid value is specified for "source-id". A valid LDEV number must be specified in "source-id" to manage the volume.	Stopped processing the request.	Make sure that the LDEV information or the command is correct, and then try the operation again.
0710-E	Failed to create a cloned volume for the volume <volume ID>. The volume type must be <i>Normal</i> .	Stopped processing the request.	Check the <code>type</code> metadata of the volume. If the <code>type</code> metadata of the volume is not <i>Normal</i> , replication of the volume might be in progress. Retry the operation after the replication finishes.
0711-E	A source volume for clone was not found. (volume_uuid: <volume ID>)	Stopped processing the request.	Specify the volume ID of an existing bootable volume in <code>volume_uuid</code> .

Message ID	Message text	Driver status	Required actions
0712-E	Failed to create a consistency group snapshot. (copy method: <copy-method>) The number of pairs in the consistency group or the number of consistency group snapshots has reached the limit.	Stopped processing the request.	Verify that the number of pairs in the consistency group is not exceeding the max permitted (8,192). If the copy method is <code>FULL</code> , make sure there are no other consistency snapshot operations in progress, and then retry the operation. If the copy method is <code>THIN</code> , delete any unnecessary snapshots for the consistency group and retry the operation.
0713-E	V-VOLs cannot be added to a consistency group.	Stopped processing the request.	Add only DP-VOLs to the consistency group. Change the copy method so that DP-VOLs are added to the consistency group.
0714-E	Failed to delete unused full copy pair. (Copy Group: <copy group >)	Stopped processing the request.	Take the actions specified in the previous message.
0716-E	No logical device exists in the storage system for the volume <volume-ID> to be added to the consistency group <consistencygroup-ID>.	Stopped processing the request.	Wait for the LDEVs to be created, and then retry the operation.
0717-E	Multiple mappings for volume <volume_id> found; no host specified.	Stopped processing the request.	Verify the volume using the storage management software. Manually delete any unnecessary mappings.
0718-E	Failed to create a thin or full copy pair because specified volume (<volume-ID>) has cascade pair of clone or thin copy pair of snapshot.	Stopped processing the request.	Delete the clone or snapshot cascade pair for the specified LDEV, and then retry the operation.

Message ID	Message text	Driver status	Required actions
0722-E	Failed to unmanage the snapshot <snapshot-ID>. This driver does not support unmanaging snapshots.	Stopped processing the request.	Use the <b>cinder snapshot-reset-state</b> command as necessary to modify the status of the snapshot.
0723-E	Failed to create a volume. An invalid value is specified for extra spec key "<key>" of the volume type. (value: <value>)	Stopped processing the request.	Set the correct value for the extra spec key for the volume type, and retry the operation.
0724-E	Failed to create a deduplicated volume. The storage system does not support deduplication, or deduplication is not enabled for the pool. (pool: <pool>)	Stopped processing the request.	Verify the storage system supports deduplication. If supported, enable deduplication of the pool, and retry the operation.
0725-E	Failed to copy the volume. (copy method: <copy-method>, P-VOL: <pvol>, S-VOL: <svo>)	Stopped processing the request.	Take the actions specified in the previous message.
0726-E	A volume or snapshot cannot be deleted. The logical device consistency for the volume or snapshot cannot be guaranteed. (LDEV: <LDEV>)	Stopped processing the request.	After backing up any required data, refer to the storage user's guide, and then initialize data reduction.
0727-E	Failed to change the volume type. An invalid value is specified for extra spec key "<key>" of the volume type after change. (value: <value>)	Stopped processing the request.	Specify a valid value for extra spec key <key> for the volume type after the change, and then retry the operation.
0728-E	The volume type change could not be completed. (LDEV: <LDEV>)	Stopped processing the request.	Take the actions specified in the previous message.

Message ID	Message text	Driver status	Required actions
0730-E	A newer version of the REST API is required. (current: <current_version>, required: <required_version> or newer)	Stopped processing the request.	Update the REST API server to the required version.
0731-E	Failed to communicate with the REST API server. (exception: <exception>, message: <message>, method: <method>, url: <url>, params: <params>, body: <body>)	Stopped processing the request.	Remove the cause of the error by following the message output by the HTTP library.
0732-E	The REST API failed. (source: <errorSource>, ID: <messageId>, message: <message>, cause: <cause>, solution: <solution>, code: <errorCode>, method: <method>, url: <url>, params: <params>, body: <body>)	Stopped processing the request.	Remove the cause of the error by following the message output by the REST API server. If the "code" value in the message is {u'SSB1': u'2E13', u'SSB2': u'6003'}, run the <b>cinder migrate</b> command with the <b>--force-host-copy True</b> option.
0733-E	The REST API timed out. (job ID: <job_id>, job status: <status>, job state: <state>, method: <method>, url: <url>, params: <params>, body: <body>)	Stopped processing the request.	Verify the REST API operation log and storage log, and then respond to the cause of the timeout. Verify volume status by using the storage management software. If any unnecessary volumes exist, remove them manually.
0734-E	The REST API failed. (HTTP status code: <status_code>, response body: <response_body>, method: <method>, url: <url>, params: <params>, body: <body>)	Stopped processing the request.	Verify the REST API server operation log.

Message ID	Message text	Driver status	Required actions
0735-E	Failed to create a consistency group snapshot. V-VOLs exist in the consistency group. (group: <group-ID>, group snapshot: <group-snapshot-ID>, group type: <group-type-ID>, volumes: <volume-ID>[, <volume-ID>...], snapshots: <snapshot-ID>[, <snapshot-ID>...])	Stopped processing the request.	Snapshots for volumes in the consistency group cannot be created because V-VOLs exist in the consistency group. Delete the volumes indicated in the message or delete the consistent_group_snapshot_enabled attribute of the group type, and then retry the operation.
0736-E	Failed to delete a {volume   snapshot} in a {group   group snapshot}. ({group   group snapshot}: <{group   group-snapshot}-ID>, {volume   snapshot}: <{volume   snapshot}-ID>, LDEV: <LDEV>, reason: <reason>)	Stopped processing the request.	Take the actions specified in the previous message.
0737-E	Failed to create a volume snapshot in a group snapshot that does not guarantee consistency. (group: <group-ID>, group snapshot: <group-snapshot-ID>, group type: <group-type-ID>, volume: <volume-ID>, snapshot: <snapshot-ID>)	Stopped processing the request.	Refer to previous messages and eliminate the cause of the failure. Then create a snapshot of the volume specified in this message.
0738-E	Failed to migrate a volume. The volume status must be 'available'. (volume: <volume-ID>, status: <status>)	Stopped processing the request.	Run the <b>cinder migrate</b> command with the <b>--force-host-copy True</b> option.

Message ID	Message text	Driver status	Required actions
0739-E	The Simple REST API failed. (source: <i>&lt;error-source&gt;</i> , ID: <i>&lt;message-ID&gt;</i> , message: <i>&lt;message&gt;</i> , cause: <i>&lt;cause&gt;</i> , solution: <i>&lt;solution&gt;</i> , code: <i>&lt;error-code&gt;</i> )	Stopped processing the request.	Take the actions specified in the previous message. If <code>SIMPLE_REST</code> is specified for the <code>hitachi_storage_cli</code> parameter, make sure that the model of the storage system whose ID is specified by <code>hitachi_storage_id</code> is VSP F350, F370, F700, F900 or VSP G350, G370, G700, G900. If the model is neither VSP F350, F370, F700, F900 nor VSP G350, G370, G700, G900, specify <code>REST</code> for the <code>hitachi_storage_cli</code> parameter or omit the parameter value.
0740-E	The Simple REST API timed out. (request ID: <i>&lt;request-ID&gt;</i> , command progress: <i>&lt;progress&gt;</i> , command result: <i>&lt;result&gt;</i> )	Stopped processing the request.	Check the REST API server operation log or the storage log to address the cause of the timeout.
0741-E	The Simple REST API failed. (HTTP status code: <i>&lt;status-code&gt;</i> , response body: <i>&lt;response-body&gt;</i> )	Stopped processing the request.	Check the REST API server operation log.
0742-E	Failed to attach the volume to the host because the server connection management object corresponding to the host was not found in the storage system. (server nickname: <i>&lt;server-nickname&gt;</i> , volume: <i>&lt;volume-ID&gt;</i> )	Stopped processing the request.	Create a server connection management object in the storage system. Alternatively, specify <code>True</code> for the <code>hitachi_server_auto_create</code> parameter.

Message ID	Message text	Driver status	Required actions
0743-E	Failed to initialize volume connection because the extra spec key "hbsd:target_ports" is set for the volume type when hitachi_storage_cli parameter is set to "SIMPLE_REST". (volume: <volume-ID>, volume type: <volume type>, hbsd:target_ports: <hbsd:target_ports>)	Stopped processing the request.	Delete the extra spec key <code>hbsd:target_ports</code> , and then retry the operation.
0744-E	Failed to create a server connection management object in the storage system because the number of used objects has reached the limit. (server nickname: <server-nickname>, protocol: <protocol>, OS type: <OS-type>, OS type option: <OS-type-option>, iSCSI authentication method: <iSCSI-authentication-method>, iSCSI mutual setting: <iSCSI-mutual-setting>)	Stopped processing the request.	Delete unnecessary server connection management objects in the storage system.
0745-E	Failed to associate a server connection management object with a port in the storage system because the number of objects that can be associated with a port has reached the limit. (server nickname: <server-nickname>, connector ID: <connector ID>, ports: <ports>)	Stopped processing the request.	Delete unnecessary server connection management objects that are associated with the port.

Message ID	Message text	Driver status	Required actions
0746-E	Failed to attach the volume to the host because the path setting for the server connection management object corresponding to the host is invalid. (server nickname: <server-nickname>, volume: <volume-ID>, ports: <port>[, <port>...])	Stopped processing the request.	From the path setting for the server connection management object, delete any ports that are not specified for the <code>hitachi_target_ports</code> parameter or for the <code>hitachi_compute_target_ports</code> parameter. Alternatively, specify <code>True</code> for the <code>hitachi_server_auto_create</code> parameter.
0747-E	Failed to initialize volume connection because no active WWN was found for the connector. (WWN: <WWN>[, <WWN> ...], volume: <volume-ID>)	Stopped processing the request.	Check the fabric network configuration, and configure the network so that active WWNs can be found.
0748-E	Failed to initialize volume connection because no port with an active WWN was found. (port, WWN: <port>, <WWN>[, port, WWN: <port>, <WWN>...], volume: <volume-ID>)	Stopped processing the request.	Check the fabric network configuration, and configure the network so that the ports with an active WWN can be found.
0749-E	The Fibre Channel Zone Manager is not available. The Fibre Channel Zone Manager must be up and running when <code>hitachi_port_scheduler</code> parameter is set to <code>True</code> .	Stopped processing the request.	Revise the settings of Fibre Channel Zone Manager so that it can run.
0750-E	Failed to initialize volume connection because no available resource of host group or wwn was found. (ports: <port>)	Stopped processing the request.	Revise the host groups or WWNs assigned to the port to secure available resources.

Message ID	Message text	Driver status	Required actions
0761-E	Failed to create the group (group: <group-ID>). This driver does not support generic volume groups.	Stopped processing the request.	Use the <b>cinder group-delete</b> command to delete the created cinder group object.

## Messages output by the command **hbsdgetinfo**

Message text	Driver status	Required actions
<b>hbsdgetinfo</b> command started.	Continues processing the request.	None.
<b>hbsdgetinfo</b> command completed successfully.	Continues processing the request.	None.
output to <i>pathDesignated/hbsdgetinfo-yyyymmddhhmmss.tar.gz</i> .	Continues processing the request.	None.
creating directory ... {succeeded   failed}	Continues processing the request.	None.
"<list of collection files>   <list of collection commands>" is not found	Has stopped processing the requests.	Reinstall the driver.
"<collection relevant files>   <collection commands>" is not found	Continues processing the request.	None.
copying "<fileName>" ... {succeeded   failed}.	Continues processing the request.	None.
executing "<commandName>" ... {succeeded   failed   skipped}.	Continues processing the request.	None.
archiving files ... {succeeded   failed}.	Continues processing the request.	None.

Message text	Driver status	Required actions
<b>hbsdgetinfo</b> is already running	Has stopped processing the requests.	None.
<b>hbsdgetinfo</b> [-d directory] [-e cinder]	Has stopped processing the requests.	Check and, if necessary, revise the specified arguments, and then try the operation again.
directory name is too long.	Has stopped processing the requests.	Check and, if necessary, revise the specified directory.
"<pass which you designated in -d>" is not a directory	Has stopped processing the requests.	Specify a directory.
"<group name which you designated in -e>" is not a group name	Has stopped processing the requests.	Check and if necessary, revise the specified group name.

## Messages output by the installer

Message text	Driver installer status	Required actions
---- <service name> service is running	Installer has stopped.	Stop the Cinder service.

---

## Appendix A: OpenStack overview

This appendix provides overviews of OpenStack and Cinder.

### About OpenStack

OpenStack is open source software for setting up a cloud environment of the IaaS layer. By linking components, OpenStack automatically combines necessary resources from the hardware resource pool that contains servers, storages, and network devices to provide users or groups with a private-server environment.

The list of the main OpenStack components is shown in the following table.

Component	Feature	Description
OpenStack Compute (Nova)	Hypervisor control	Manages virtual machines in a multi-hypervisor environment.
OpenStack Image (Glance)	Image, Snapshot control	Manages VM images.
OpenStack Network (Neutron)	Virtual network control	Manages L2/L3 networks.
OpenStack Object Storage (Swift)	Object storage control	Provides highly-available distributed object storage.
OpenStack Block Storage (Cinder)	Block storage control	Provides permanent block storage to VM.
OpenStack Identity (Keystone)	Integrated authentication infrastructure	Manages authentication and operation authorization common to each component.
OpenStack Dashboard (Horizon)	Self-service WebUI	Provides the self-service Web portal.

## Cinder overview

Cinder is an OpenStack service component that provides persistent block device storage to VM OpenStack Compute instances as a volume. Data in a Cinder volume persists (remains undeleted) when the volume is detached from a VM instance. Since the data remains on the block device corresponding to the volume, it can always be reattached by changing the connection to other VM instances. In addition, high I/O performance is expected because it has direct access to the block device corresponding to the volume from the VM.

Storage providers include a Cinder driver for their storage devices so they can be used to provide storage in an OpenStack environment.

## Cinder commands

The OpenStack Cinder commands can operate backends through the OpenStack Cinder API. Before using the commands, you must configure the available Keystone user authentication for the environment variables.

The OpenStack configuration installer included in each distribution creates the file containing the authentication information on the controller node. Load this file into the environment variables using the **source** command. The following is an example of an OpenStack environment configuration with the **packstack** command for the Red Hat OpenStack Platform.

```
# source /root/keystonerc_admin
```

Authentication information for admin user is described in `keystonerc_admin` and placed under `/root`.

For details about **cinder** command options, see the help message output by entering the following:

```
# /usr/bin/cinder help
```

Cinder functions available via CLI vary according to the version of the API. Refer to online help, such as OpenStack Command-Line Interface Reference, for details about CLI support for Cinder functions.

## OpenStack commands

Commands of all OpenStack projects are being integrated into **openstack** commands. For example, **cinder create** is being replaced by **openstack volume create**. Using **cinder** commands is recommended because not all volume use cases are available in the **openstack** commands.

---

## Appendix B: Block Storage Driver for OpenStack License

Apache License 2.0 is applied to Block Storage Driver for OpenStack.  
# Copyright (C) 2014, 2018, Hitachi, Ltd.  
#  
# Licensed under the Apache License, Version 2.0 (the "License"); you may  
# not use this file except in compliance with the License. You may obtain  
# a copy of the License at  
#  
# <http://www.apache.org/licenses/LICENSE-2.0>  
#  
# Unless required by applicable law or agreed to in writing, software  
# distributed under the License is distributed on an "AS IS" BASIS, WITHOUT  
# WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the  
# License for the specific language governing permissions and limitations  
# under the License.

# Glossary

## **Consistency group (CG)**

A consistency group allows a storage device to take a snapshot of multiple volumes simultaneously so that all of the snapshots have the same point-in-time data consistency.

## **DP pool**

Area in which Dynamic Provisioning manages virtual volumes (DP-VOL).

## **DP-VOL**

A virtual volume where physical storage space is only consumed when needed (thin provisioning).

## **Dynamic Provisioning**

Dynamic Provisioning is Hitachi's implementation of thin provisioning. Instead of reserving a fixed amount of storage for a volume, capacity from an available pool (DP pool) is used at the time data is written to the storage.

## **Generic volume group (GVG)**

A group of volumes. This concept is an extension of consistency group. A GVG either guarantees or does not guarantee consistency. A GVG that guarantees consistency is similar to a consistency group, but is operated through different commands. A GVG is also simply referred to as a group.

## **In-band**

In the in-band management method, the Configuration Manager REST API server connects to the storage system through a SAN.

## **Out-of-band**

In the out-of-band management method, the Configuration Manager REST API server connects to the storage system through a LAN. This is the default communication mode for the Configuration Manager REST API server.

## **Snapshot**

Data unit in which data of a volume at any point in time is stored.

## **Thin Image (Clone)**

A copy method where the data on the source volume (DP-VOL) is copied asynchronously to the destination volume (DP-VOL).

## **Thin Image (Snapshot)**

A copy method where a snapshot of the data on the source volume (DP-VOL) is created on the copy destination volume (DP-VOL).

## **TI pool**

Thin Image pool used by Thin Image.

## Hitachi Vantara



Corporate Headquarters

2845 Lafayette Street

Santa Clara, CA 95050-2639 USA

[HitachiVantara.com](http://HitachiVantara.com) | [community.HitachiVantara.com](http://community.HitachiVantara.com)

Contact Information

USA: 1-800-446-0744

Global: 1-858-547-4526

[HitachiVantara.com/contact](http://HitachiVantara.com/contact)